FlyCapture2 C 2.13.3.31

Generated by Doxygen 1.8.13

Contents

| 1 | Soft | ware Li | censing I | nformation | 1 | | | | |
|---|-----------------|----------|------------|---------------------------------------|----|--|--|--|--|
| 2 | Peprecated List | | | | | | | | |
| 3 | 3 Module Index | | | | | | | | |
| | 3.1 | Module | es | | 5 | | | | |
| 4 | Data | a Struct | ure Index | | 7 | | | | |
| | 4.1 | Data S | Structures | | 7 | | | | |
| 5 | File | Index | | | 9 | | | | |
| | 5.1 | File Lis | st | | 9 | | | | |
| 6 | Mod | lule Doc | cumentati | on | 11 | | | | |
| | 6.1 | Bus M | anager Op | peration | 11 | | | | |
| | | 6.1.1 | Detailed | Description | 12 | | | | |
| | | 6.1.2 | Function | Documentation | 12 | | | | |
| | | | 6.1.2.1 | fc2DiscoverGigECameras() | 12 | | | | |
| | | | 6.1.2.2 | fc2FireBusReset() | 13 | | | | |
| | | | 6.1.2.3 | fc2ForceAllIPAddressesAutomatically() | 13 | | | | |
| | | | 6.1.2.4 | fc2ForceIPAddressAutomatically() | 14 | | | | |
| | | | 6.1.2.5 | fc2ForceIPAddressToCamera() | 14 | | | | |
| | | | 6.1.2.6 | fc2GetCameraFromIndex() | 14 | | | | |
| | | | 6.1.2.7 | fc2GetCameraFromIPAddress() | 16 | | | | |
| | | | 6.1.2.8 | fc2GetCameraFromSerialNumber() | 16 | | | | |
| | | | 6.1.2.9 | fc2GetCameraSerialNumberFromIndex() | 17 | | | | |

ii CONTENTS

| | | 6.1.2.10 | fc2GetDeviceFromIndex() | 17 |
|-----|-------|-------------|-------------------------------|----|
| | | 6.1.2.11 | fc2GetInterfaceTypeFromGuid() | 18 |
| | | 6.1.2.12 | fc2GetNumOfCameras() | 18 |
| | | 6.1.2.13 | fc2GetNumOfDevices() | 19 |
| | | 6.1.2.14 | fc2GetTopology() | 19 |
| | | 6.1.2.15 | fc2GetUsbLinkInfo() | 19 |
| | | 6.1.2.16 | fc2GetUsbPortStatus() | 20 |
| | | 6.1.2.17 | fc2lsCameraControlable() | 20 |
| | | 6.1.2.18 | fc2ReadPhyRegister() | 21 |
| | | 6.1.2.19 | fc2RegisterCallback() | 21 |
| | | 6.1.2.20 | fc2RescanBus() | 22 |
| | | 6.1.2.21 | fc2UnregisterCallback() | 22 |
| | | 6.1.2.22 | fc2WritePhyRegister() | 22 |
| 6.2 | Conne | ction and I | mage Retrieval | 25 |
| | 6.2.1 | Detailed | Description | 25 |
| | 6.2.2 | Function | Documentation | 25 |
| | | 6.2.2.1 | fc2Connect() | 26 |
| | | 6.2.2.2 | fc2Disconnect() | 26 |
| | | 6.2.2.3 | fc2GetConfiguration() | 26 |
| | | 6.2.2.4 | fc2lsConnected() | 27 |
| | | 6.2.2.5 | fc2RetrieveBuffer() | 27 |
| | | 6.2.2.6 | fc2SetCallback() | 28 |
| | | 6.2.2.7 | fc2SetConfiguration() | 28 |
| | | 6.2.2.8 | fc2SetUserBuffers() | 29 |
| | | 6.2.2.9 | fc2StartCapture() | 29 |
| | | 6.2.2.10 | fc2StartCaptureCallback() | 30 |
| | | 6.2.2.11 | fc2StartSyncCapture() | 31 |
| | | 6.2.2.12 | fc2StartSyncCaptureCallback() | 31 |
| | | 6.2.2.13 | fc2StopCapture() | 32 |
| | | 6.2.2.14 | fc2WaitForBufferEvent() | 32 |

CONTENTS

| 6.3 | Informa | nation and Properties | | | | | | |
|-----|---------|-----------------------|-----------------------------------|----|--|--|--|--|
| | 6.3.1 | Detailed I | Description | 34 | | | | |
| | 6.3.2 | Function | Documentation | 34 | | | | |
| | | 6.3.2.1 | fc2GetCameraInfo() | 34 | | | | |
| | | 6.3.2.2 | fc2GetProperty() | 35 | | | | |
| | | 6.3.2.3 | fc2GetPropertyInfo() | 35 | | | | |
| | | 6.3.2.4 | fc2SetProperty() | 36 | | | | |
| | | 6.3.2.5 | fc2SetPropertyBroadcast() | 36 | | | | |
| 6.4 | Genera | al Purpose | Input / Output | 38 | | | | |
| | 6.4.1 | Detailed I | Description | 38 | | | | |
| | 6.4.2 | Function | Documentation | 38 | | | | |
| | | 6.4.2.1 | fc2GetGPIOPinDirection() | 38 | | | | |
| | | 6.4.2.2 | fc2SetGPIOPinDirection() | 39 | | | | |
| | | 6.4.2.3 | fc2SetGPIOPinDirectionBroadcast() | 39 | | | | |
| 6.5 | Trigger | | | 41 | | | | |
| | 6.5.1 | Detailed I | Description | 41 | | | | |
| | 6.5.2 | Function | Documentation | 41 | | | | |
| | | 6.5.2.1 | fc2FireSoftwareTrigger() | 41 | | | | |
| | | 6.5.2.2 | fc2FireSoftwareTriggerBroadcast() | 42 | | | | |
| | | 6.5.2.3 | fc2GetTriggerDelay() | 42 | | | | |
| | | 6.5.2.4 | fc2GetTriggerDelayInfo() | 43 | | | | |
| | | 6.5.2.5 | fc2GetTriggerMode() | 43 | | | | |
| | | 6.5.2.6 | fc2GetTriggerModeInfo() | 44 | | | | |
| | | 6.5.2.7 | fc2SetTriggerDelay() | 44 | | | | |
| | | 6.5.2.8 | fc2SetTriggerDelayBroadcast() | 45 | | | | |
| | | 6.5.2.9 | fc2SetTriggerMode() | 46 | | | | |
| | | 6.5.2.10 | fc2SetTriggerModeBroadcast() | 46 | | | | |
| 6.6 | Strobe | | | 48 | | | | |
| | 6.6.1 | Detailed I | Description | 48 | | | | |
| | 6.6.2 | Function | Documentation | 48 | | | | |

iv CONTENTS

| | | 6.6.2.1 | fc2GetStrobe() | . 48 |
|-----|--------|------------|-------------------------------|------|
| | | 6.6.2.2 | fc2GetStrobeInfo() | . 49 |
| | | 6.6.2.3 | fc2SetStrobe() | . 49 |
| | | 6.6.2.4 | fc2SetStrobeBroadcast() | . 50 |
| 6.7 | Look L | Jp Table . | | . 51 |
| | 6.7.1 | Detailed | Description | . 51 |
| | 6.7.2 | Function | Documentation | . 51 |
| | | 6.7.2.1 | fc2EnableLUT() | . 51 |
| | | 6.7.2.2 | fc2GetActiveLUTBank() | . 52 |
| | | 6.7.2.3 | fc2GetLUTBankInfo() | . 52 |
| | | 6.7.2.4 | fc2GetLUTChannel() | . 53 |
| | | 6.7.2.5 | fc2GetLUTInfo() | . 53 |
| | | 6.7.2.6 | fc2SetActiveLUTBank() | . 54 |
| | | 6.7.2.7 | fc2SetLUTChannel() | . 54 |
| 6.8 | Memoi | ry Channe | els | . 56 |
| | 6.8.1 | Detailed | Description | . 56 |
| | 6.8.2 | Function | Documentation | . 56 |
| | | 6.8.2.1 | fc2GetEmbeddedImageInfo() | . 56 |
| | | 6.8.2.2 | fc2GetMemoryChannel() | . 57 |
| | | 6.8.2.3 | fc2GetMemoryChannelInfo() | . 57 |
| | | 6.8.2.4 | fc2RestoreFromMemoryChannel() | . 58 |
| | | 6.8.2.5 | fc2SaveToMemoryChannel() | . 58 |
| | | 6.8.2.6 | fc2SetEmbeddedImageInfo() | . 59 |
| 6.9 | Regist | er Operati | on | . 60 |
| | 6.9.1 | Detailed | Description | . 60 |
| | 6.9.2 | Function | Documentation | . 60 |
| | | 6.9.2.1 | fc2GetRegisterString() | . 60 |
| | | 6.9.2.2 | fc2ReadRegister() | . 61 |
| | | 6.9.2.3 | fc2ReadRegisterBlock() | . 61 |
| | | 6.9.2.4 | fc2WriteRegister() | . 62 |

CONTENTS

| | | 6.9.2.5 | fc2WriteRegisterBlock() | 62 |
|------|--------|------------|------------------------------------|----|
| | | 6.9.2.6 | fc2WriteRegisterBroadcast() | 63 |
| 6.10 | DCAM | Formats | | 64 |
| | 6.10.1 | Detailed | Description | 64 |
| | 6.10.2 | Function | Documentation | 64 |
| | | 6.10.2.1 | fc2GetVideoModeAndFrameRate() | 64 |
| | | 6.10.2.2 | fc2GetVideoModeAndFrameRateInfo() | 65 |
| | | 6.10.2.3 | fc2SetVideoModeAndFrameRate() | 65 |
| 6.11 | Format | 7 | | 66 |
| | 6.11.1 | Detailed | Description | 66 |
| | 6.11.2 | Function | Documentation | 66 |
| | | 6.11.2.1 | fc2GetFormat7Configuration() | 66 |
| | | 6.11.2.2 | fc2GetFormat7Info() | 67 |
| | | 6.11.2.3 | fc2SetFormat7Configuration() | 67 |
| | | 6.11.2.4 | fc2SetFormat7ConfigurationPacket() | 68 |
| | | 6.11.2.5 | fc2ValidateFormat7Settings() | 68 |
| 6.12 | GVCP | Register C | Operation | 69 |
| | 6.12.1 | Detailed | Description | 69 |
| | 6.12.2 | Function | Documentation | 69 |
| | | 6.12.2.1 | fc2ReadGVCPMemory() | 69 |
| | | 6.12.2.2 | fc2ReadGVCPRegister() | 70 |
| | | 6.12.2.3 | fc2ReadGVCPRegisterBlock() | 70 |
| | | 6.12.2.4 | fc2WriteGVCPMemory() | 71 |
| | | 6.12.2.5 | fc2WriteGVCPRegister() | 71 |
| | | 6.12.2.6 | fc2WriteGVCPRegisterBlock() | 72 |
| | | 6.12.2.7 | fc2WriteGVCPRegisterBroadcast() | 72 |
| 6.13 | GigE p | roperty ma | anipulation | 73 |
| | 6.13.1 | Detailed | Description | 73 |
| | 6.13.2 | Function | Documentation | 73 |
| | | 6.13.2.1 | fc2DiscoverGigEPacketSize() | 73 |

vi

| | | 6.13.2.2 | fc2GetGigEProperty() | 74 |
|------|---------|-------------|----------------------------------|----|
| | | 6.13.2.3 | fc2SetGigEProperty() | 74 |
| 6.14 | GigE in | nage settir | ngs | 75 |
| | 6.14.1 | Detailed | Description | 75 |
| | 6.14.2 | Function | Documentation | 75 |
| | | 6.14.2.1 | fc2GetGigEImageSettings() | 75 |
| | | 6.14.2.2 | fc2GetGigEImageSettingsInfo() | 76 |
| | | 6.14.2.3 | fc2GetGigEImagingMode() | 76 |
| | | 6.14.2.4 | fc2QueryGigEImagingMode() | 76 |
| | | 6.14.2.5 | fc2SetGigEImageSettings() | 78 |
| | | 6.14.2.6 | fc2SetGigEImagingMode() | 78 |
| 6.15 | GigE in | nage binni | ing settings | 80 |
| | 6.15.1 | Detailed | Description | 80 |
| | 6.15.2 | Function | Documentation | 80 |
| | | 6.15.2.1 | fc2GetGigEImageBinningSettings() | 80 |
| | | 6.15.2.2 | fc2SetGigEImageBinningSettings() | 80 |
| 6.16 | GigE in | nage strea | am configuration | 82 |
| | 6.16.1 | Detailed | Description | 82 |
| | 6.16.2 | Function | Documentation | 82 |
| | | 6.16.2.1 | fc2GetGigEConfig() | 82 |
| | | 6.16.2.2 | fc2GetGigEStreamChannelInfo() | 83 |
| | | 6.16.2.3 | fc2GetNumStreamChannels() | 83 |
| | | 6.16.2.4 | fc2SetGigEConfig() | 83 |
| | | 6.16.2.5 | fc2SetGigEStreamChannelInfo() | 84 |
| 6.17 | Image | Operation | | 85 |
| | 6.17.1 | Detailed | Description | 86 |
| | 6.17.2 | Function | Documentation | 86 |
| | | 6.17.2.1 | fc2CalculateImageStatistics() | 86 |
| | | 6.17.2.2 | fc2ConvertImage() | 86 |
| | | 6.17.2.3 | fc2ConvertImageTo() | 87 |

CONTENTS vii

| | 6.17.2.4 fc2Cr | eateImage() | | | | | | | | . 87 |
|--------|-------------------|--|----------------------------|----------------------------|--|---|--|---|--|---|
| | 6.17.2.5 fc2De | estroyImage() | | | | | | | | . 88 |
| | 6.17.2.6 fc2De | etermineBitsPerPixel | () | | | | | | | . 88 |
| | 6.17.2.7 fc2G | etDefaultColorProces | ssing() | | | | | | | . 89 |
| | 6.17.2.8 fc2Ge | etDefaultOutputForm | nat() | | | | | | | . 89 |
| | 6.17.2.9 fc2Ge | etImageColorProces | sing() | | | | | | | . 89 |
| | 6.17.2.10 fc2G | etImageData() | | | | | | | | . 90 |
| | 6.17.2.11 fc2Ge | etImageDimensions(|) | | | | | | | . 90 |
| | 6.17.2.12 fc2Ge | etImageMetadata() | | | | | | | | . 91 |
| | 6.17.2.13 fc2Ge | etImageTimeStamp() |) | | | | | | | . 91 |
| | 6.17.2.14 fc2Sa | avelmage() | | | | | | | | . 91 |
| | 6.17.2.15 fc2Sa | aveImageWithOption | () | | | | | | | . 92 |
| | 6.17.2.16 fc2Se | atDefaultColorProces | ssing() | | | | | | | . 92 |
| | 6.17.2.17 fc2Se | atDefaultOutputForm | at() | | | | | | | . 93 |
| | 6.17.2.18 fc2Se | tImageColorProcess | sing() | | | | | | | . 93 |
| | 6.17.2.19 fc2Se | etImageData() | | | | | | | | . 94 |
| | 6.17.2.20 fc2Se | etImageDimensions() |) | | | | | | | . 94 |
| Image | Statistics Operat | ion | | | | | | | | . 95 |
| 6.18.1 | Detailed Descri | ption | | | | | | | | . 96 |
| 6.18.2 | Function Docum | nentation | | | | | | | | . 96 |
| | 6.18.2.1 fc2Cr | eateImageStatistics(| () | | | | | | | . 96 |
| | 6.18.2.2 fc2De | estroyImageStatistics | s() | | | | | | | . 96 |
| | 6.18.2.3 fc2Ge | etChannelHistogram | () | | | | | | | . 96 |
| | 6.18.2.4 fc2Ge | etChannelMean() . | | | | | | | | . 97 |
| | 6.18.2.5 fc2Ge | etChannelNumPixel\ | /alues() . | | | | | | | . 97 |
| | 6.18.2.6 fc2Ge | etChannelPixelValue | Range() . | | | | | | | . 98 |
| | 6.18.2.7 fc2Ge | etChannelRange() | | | | | | | | . 98 |
| | 6.18.2.8 fc2Ge | etChannelStatus() . | | | | | | | | . 99 |
| | 6.18.2.9 fc2Ge | etImageStatistics() | | | | | | | | . 99 |
| | 6.18.2.10 fc2lm | ageStatisticsDisable | eAll() | | | | | | | . 100 |
| | 6.18.1 | 6.17.2.5 fc2De 6.17.2.6 fc2De 6.17.2.7 fc2Ge 6.17.2.8 fc2Ge 6.17.2.9 fc2Ge 6.17.2.10 fc2Ge 6.17.2.11 fc2Ge 6.17.2.12 fc2Ge 6.17.2.13 fc2Ge 6.17.2.14 fc2Se 6.17.2.15 fc2Se 6.17.2.16 fc2Se 6.17.2.17 fc2Se 6.17.2.18 fc2Se 6.17.2.19 fc2Se 6.17.2.20 fc2Se 6.17.2.20 fc2Se 6.18.2.1 fc2Cr 6.18.2.2 fc2Ge 6.18.2.3 fc2Ge 6.18.2.4 fc2Ge 6.18.2.5 fc2Ge 6.18.2.6 fc2Ge 6.18.2.7 fc2Ge 6.18.2.8 fc2Ge 6.18.2.9 fc2Ge 6.18.2.9 fc2Ge | 6.17.2.5 fc2DestroyImage() | 6.17.2.5 fc2DestroyImage() | 6.17.2.5 fc2DestroyImage() 6.17.2.6 fc2DetermineBitsPerPixel() 6.17.2.7 fc2GetDefaultColorProcessing() 6.17.2.8 fc2GetDefaultOutputFormat() 6.17.2.9 fc2GetImageColorProcessing() 6.17.2.10 fc2GetImageData() 6.17.2.11 fc2GetImageDimensions() 6.17.2.12 fc2GetImageMetadata() 6.17.2.13 fc2GetImageTimeStamp() 6.17.2.14 fc2SaveImage() 6.17.2.15 fc2SaveImageWithOption() 6.17.2.16 fc2SetDefaultColorProcessing() 6.17.2.17 fc2SetDefaultColorProcessing() 6.17.2.18 fc2SetImageColorProcessing() 6.17.2.19 fc2SetImageData() 6.17.2.19 fc2SetImageData() 6.18.2.1 fc2CreateImageDimensions() Image Statistics Operation 6.18.2 Function Documentation 6.18.2.1 fc2CreateImageStatistics() 6.18.2.3 fc2GetChannelHistogram() 6.18.2.4 fc2GetChannelHistogram() 6.18.2.5 fc2GetChannelNumPixelValueS() 6.18.2.6 fc2GetChannelRange() 6.18.2.7 fc2GetChannelRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.9 fc2GetImageStatistics() | 6.17.2.5 fc2DestroyImage() 6.17.2.6 fc2DetermineBitsPerPixel() 6.17.2.7 fc2GetDefaultColorProcessing() 6.17.2.8 fc2GetDefaultColorProcessing() 6.17.2.9 fc2GetImageColorProcessing() 6.17.2.10 fc2GetImageData() 6.17.2.11 fc2GetImageDimensions() 6.17.2.12 fc2GetImageMetadata() 6.17.2.13 fc2GetImageTimeStamp() 6.17.2.14 fc2SaveImage() 6.17.2.15 fc2SaveImageWithOption() 6.17.2.16 fc2SetDefaultColorProcessing() 6.17.2.17 fc2SetDefaultOutputFormat() 6.17.2.18 fc2SetImageData() 6.17.2.19 fc2SetImageData() 6.17.2.19 fc2SetImageDimensions() Image Statistics Operation 6.18.1 Detailed Description 6.18.2 Function Documentation 6.18.2.1 fc2CreateImageStatistics() 6.18.2.3 fc2GetChannelHistogram() 6.18.2.4 fc2GetChannelHistogram() 6.18.2.5 fc2GetChannelNumPixelValues() 6.18.2.6 fc2GetChannelRange() 6.18.2.7 fc2GetChannelRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.9 fc2GetImageStatistics() | 6.17.2.5 fc2DestroyImage() 6.17.2.6 fc2DetermineBitsPerPixel() 6.17.2.7 fc2GetDefaultColorProcessing() 6.17.2.8 fc2GetDefaultColorProcessing() 6.17.2.9 fc2GetImageColorProcessing() 6.17.2.10 fc2GetImageData() 6.17.2.11 fc2GetImageDimensions() 6.17.2.12 fc2GetImageMetadata() 6.17.2.13 fc2GetImageTimeStamp() 6.17.2.14 fc2SaveImage() 6.17.2.15 fc2SaveImageWithOption() 6.17.2.16 fc2SetDefaultColorProcessing() 6.17.2.17 fc2SetDefaultColorProcessing() 6.17.2.18 fc2SetImageColorProcessing() 6.17.2.19 fc2SetImageData() 6.17.2.10 fc2SetImageData() 6.17.2.11 fc2CestImageData() 6.17.2.12 fc2CestImageData() 6.17.2.13 fc2GetChannelPixelValues() 6.18.2.1 fc2CreateImageStatistics() 6.18.2.2 fc2GetChannelPixelValueRange() 6.18.2.3 fc2GetChannelPixelValueRange() 6.18.2.6 fc2GetChannelPixelValueRange() 6.18.2.7 fc2GetChannelPixelValueRange() 6.18.2.8 fc2GetChannelPixelValueRange() 6.18.2.9 fc2GetImageStatistics() | 6.17.2.5 fc2DestroyImage() 6.17.2.6 fc2DetermineBitsPerPixel() 6.17.2.7 fc2GetDefaultColorProcessing() 6.17.2.8 fc2GetDefaultOutputFormat() 6.17.2.9 fc2GetImageColorProcessing() 6.17.2.10 fc2GetImageData() 6.17.2.11 fc2GetImageDimensions() 6.17.2.12 fc2GetImageMetadata() 6.17.2.13 fc2GetImageMetadata() 6.17.2.14 fc2SaveImageWithOption() 6.17.2.15 fc2SaveImageWithOption() 6.17.2.16 fc2SetDefaultColorProcessing() 6.17.2.17 fc2SetDefaultOutputFormat() 6.17.2.18 fc2SetImageColorProcessing() 6.17.2.19 fc2SetImageData() 6.17.2.20 fc2SetImageData() 6.17.2.21 fc2CeatImageData() 6.17.2.21 fc2CeatImageData() 6.17.2.21 fc2CeatImageData() 6.17.2.21 fc2CeatImageData() 6.17.2.21 fc2CeatImageData() 6.18.2.1 fc2CeatImageData() 6.18.2.2 fc2DestroyImageStatistics() 6.18.2.3 fc2GetChannelHistogram() 6.18.2.4 fc2GetChannelHistogram() 6.18.2.5 fc2GetChannelNumPixelValues() 6.18.2.6 fc2GetChannelPixelValueRange() 6.18.2.8 fc2GetChannelPixelValueRange() 6.18.2.8 fc2GetChannelPixelValueRange() 6.18.2.9 fc2GetImageStatistics() | 6.17.2.5 fc2DestroyImage() 6.17.2.6 fc2DetermineBitsPerPixeI() 6.17.2.7 fc2GetDefaultColorProcessing() 6.17.2.8 fc2GetDefaultCutputFormat() 6.17.2.9 fc2GetImageColorProcessing() 6.17.2.10 fc2GetImageData() 6.17.2.11 fc2GetImageDimensions() 6.17.2.12 fc2GetImageTimeStamp() 6.17.2.13 fc2GetImageTimeStamp() 6.17.2.14 fc2SaveImage() 6.17.2.15 fc2SaveImageWithOption() 6.17.2.16 fc2SetDefaultColorProcessing() 6.17.2.17 fc2SetDefaultColorProcessing() 6.17.2.18 fc2SetImageColorProcessing() 6.17.2.19 fc2SetImageDimensions() Image Statistics Operation 6.18.1 Detailed Description 6.18.2 Function Documentation 6.18.2.1 fc2CreateImageStatistics() 6.18.2.3 fc2GetChannelHistogram() 6.18.2.4 fc2GetChannelHistogram() 6.18.2.5 fc2GetChannelNumPixelValues() 6.18.2.6 fc2GetChannelPixelValueRange() 6.18.2.8 fc2GetChannelPixelValueRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.8 fc2GetChannelRange() 6.18.2.9 fc2GetImageStatistics() | 6.18.2.2 fc2DestroyImageStatistics() 6.18.2.3 fc2GetChannelHistogram() 6.18.2.4 fc2GetChannelMean() 6.18.2.5 fc2GetChannelNumPixelValues() 6.18.2.6 fc2GetChannelPixelValueRange() 6.18.2.7 fc2GetChannelRange() |

viii CONTENTS

| | 6.18.2.11 fc2ImageStatisticsEnableAll() |
|---------------|--|
| | 6.18.2.12 fc2ImageStatisticsEnableGreyOnly() |
| | 6.18.2.13 fc2ImageStatisticsEnableHSLOnly() |
| | 6.18.2.14 fc2ImageStatisticsEnableRGBOnly() |
| | 6.18.2.15 fc2SetChannelStatus() |
| 6.19 Topolo | pgyNode Operation |
| 6.19.1 | Detailed Description |
| 6.19.2 | Function Documentation |
| | 6.19.2.1 fc2CreateTopologyNode() |
| | 6.19.2.2 fc2DestroyTopologyNode() |
| | 6.19.2.3 fc2TopologyNodeAddChild() |
| | 6.19.2.4 fc2TopologyNodeAddPortType() |
| | 6.19.2.5 fc2TopologyNodeAssignGuidToNode() |
| | 6.19.2.6 fc2TopologyNodeAssignGuidToNodeEx() |
| | 6.19.2.7 fc2TopologyNodeGetChild() |
| | 6.19.2.8 fc2TopologyNodeGetDeviceId() |
| | 6.19.2.9 fc2TopologyNodeGetGuid() |
| | 6.19.2.10 fc2TopologyNodeGetInterfaceType() |
| | 6.19.2.11 fc2TopologyNodeGetNodeType() |
| | 6.19.2.12 fc2TopologyNodeGetNumChildren() |
| | 6.19.2.13 fc2TopologyNodeGetNumPorts() |
| | 6.19.2.14 fc2TopologyNodeGetPortType() |
| 6.20 Utilitie | s |
| 6.20.1 | Detailed Description |
| 6.20.2 | Function Documentation |
| | 6.20.2.1 fc2CheckDriver() |
| | 6.20.2.2 fc2ErrorToDescription() |
| | 6.20.2.3 fc2GetDriverDeviceName() |
| | 6.20.2.4 fc2GetLibraryVersion() |
| | 6.20.2.5 fc2GetSystemInfo() |
| | |

CONTENTS

| | | 6.20.2.6 | fc2LaunchBrowser() | | 112 |
|------|--------|-----------|-----------------------------|------|---------|
| | | 6.20.2.7 | fc2LaunchCommand() | | 113 |
| | | 6.20.2.8 | fc2LaunchCommandAsync() | | 113 |
| | | 6.20.2.9 | fc2LaunchHelp() | | 113 |
| 6.21 | TypeDe | efs | | | 115 |
| | 6.21.1 | Detailed | Description | | 115 |
| | 6.21.2 | Macro De | efinition Documentation | | 115 |
| | | 6.21.2.1 | FALSE | | 115 |
| | | 6.21.2.2 | FULL_32BIT_VALUE | | 115 |
| | | 6.21.2.3 | MAX_STRING_LENGTH | | 116 |
| | | 6.21.2.4 | TRUE | | 116 |
| | 6.21.3 | Typedef [| Documentation | | 116 |
| | | 6.21.3.1 | BOOL | | 116 |
| | | 6.21.3.2 | fc2Context | | 116 |
| | | 6.21.3.3 | fc2GuiContext | | 116 |
| | | 6.21.3.4 | fc2ImageImpl | | 116 |
| | | 6.21.3.5 | fc2ImageStatisticsContext | | 117 |
| | | 6.21.3.6 | fc2TopologyNodeContext | | 117 |
| | | 6.21.3.7 | fc2VideoContext | | 117 |
| 6.22 | Enume | rations . | | | 118 |
| | 6.22.1 | Detailed | Description | | 122 |
| | 6.22.2 | Enumera | ation Type Documentation | | 122 |
| | | 6.22.2.1 | fc2BandwidthAllocation | | 123 |
| | | 6.22.2.2 | fc2BayerTileFormat | | 123 |
| | | 6.22.2.3 | fc2BusCallbackType | | 123 |
| | | 6.22.2.4 | fc2BusSpeed | | 124 |
| | | 6.22.2.5 | fc2ColorProcessingAlgorithm | | 124 |
| | | 6.22.2.6 | fc2DriverType | | 125 |
| | | 6.22.2.7 | fc2Error | | 125 |
| | | 6.22.2.8 | fc2FrameRate | | 126 |
| | | | | | |

CONTENTS

| | | 3.22.2.9 fc2GrabMode | . 127 |
|------|---------|-----------------------------------|-------|
| | | 6.22.2.10 fc2GrabTimeout | . 127 |
| | | 5.22.2.11 fc2ImageFileFormat | . 128 |
| | | 6.22.2.12 fc2InterfaceType | . 128 |
| | | 6.22.2.13 fc2Mode | . 129 |
| | | 6.22.2.14 fc2PCleBusSpeed | . 129 |
| | | 6.22.2.15 fc2PixelFormat | . 130 |
| | | 6.22.2.16 fc2PropertyType | . 130 |
| | | 6.22.2.17 fc2VideoMode | . 131 |
| 6.23 | GigE s | ecific enumerations | . 133 |
| | 6.23.1 | Detailed Description | . 133 |
| | 6.23.2 | Enumeration Type Documentation | . 133 |
| | | 6.23.2.1 fc2GigEPropertyType | . 133 |
| 6.24 | Structu | es | . 134 |
| | 6.24.1 | Detailed Description | . 135 |
| 6.25 | GigE s | ecific structures | . 136 |
| | 6.25.1 | Detailed Description | . 136 |
| 6.26 | IIDC sp | ecific structures | . 137 |
| | 6.26.1 | Detailed Description | . 137 |
| 6.27 | Image | aving structures | . 138 |
| | 6.27.1 | Detailed Description | . 139 |
| | 6.27.2 | Typedef Documentation | . 139 |
| | | 6.27.2.1 fc2AsyncCommandCallback | . 139 |
| | | 6.27.2.2 fc2BusEventCallback | . 139 |
| | | 6.27.2.3 fc2CallbackHandle | . 139 |
| | | 6.27.2.4 fc2CameraEventCallback | . 139 |
| | | 6.27.2.5 fc2ImageEventCallback | . 139 |
| | 6.27.3 | Enumeration Type Documentation | . 139 |
| | | 6.27.3.1 fc2TIFFCompressionMethod | . 139 |
| 6.28 | Video F | ecording Operation | . 141 |
| | 6.28.1 | Detailed Description | . 141 |
| | 6.28.2 | Function Documentation | . 141 |
| | | 6.28.2.1 fc2VideoAppend() | . 141 |
| | | 6.28.2.2 fc2VideoAVIOpen() | . 142 |
| | | 6.28.2.3 fc2VideoClose() | . 142 |
| | | 6.28.2.4 fc2VideoCreate() | . 143 |
| | | 6.28.2.5 fc2VideoDestroy() | . 143 |
| | | 6.28.2.6 fc2VideoH264Open() | . 143 |
| | | 6.28.2.7 fc2VideoMJPGOpen() | . 144 |
| | | 6.28.2.8 fc2VideoSetMaximumSize() | . 144 |
| 6.29 | Video s | ving structures | . 146 |
| | 6.29.1 | Detailed Description | . 146 |

CONTENTS xi

| 7 | Data | Struct | ure Docun | nentation | 147 |
|---|------|--------|------------|----------------------|-----|
| | 7.1 | fc2AVI | Option Str | uct Reference | 147 |
| | | 7.1.1 | Detailed | Description | 147 |
| | | 7.1.2 | Field Doo | cumentation | 147 |
| | | | 7.1.2.1 | frameRate | 147 |
| | | | 7.1.2.2 | reserved | 148 |
| | 7.2 | fc2BM | POption St | truct Reference | 148 |
| | | 7.2.1 | Detailed | Description | 148 |
| | | 7.2.2 | Field Doo | cumentation | 148 |
| | | | 7.2.2.1 | indexedColor_8bit | 148 |
| | | | 7.2.2.2 | reserved | 148 |
| | 7.3 | fc2Car | meraInfo S | truct Reference | 149 |
| | | 7.3.1 | Detailed | Description | 150 |
| | | 7.3.2 | Field Doo | cumentation | 150 |
| | | | 7.3.2.1 | applicationIPAddress | 151 |
| | | | 7.3.2.2 | applicationPort | 151 |
| | | | 7.3.2.3 | bayerTileFormat | 151 |
| | | | 7.3.2.4 | busNumber | 151 |
| | | | 7.3.2.5 | ccpStatus | 151 |
| | | | 7.3.2.6 | configROM | 151 |
| | | | 7.3.2.7 | defaultGateway | 152 |
| | | | 7.3.2.8 | driverName | 152 |
| | | | 7.3.2.9 | driverType | 152 |
| | | | 7.3.2.10 | firmwareBuildTime | 152 |
| | | | 7.3.2.11 | firmwareVersion | 152 |
| | | | 7.3.2.12 | gigEMajorVersion | 152 |
| | | | 7.3.2.13 | gigEMinorVersion | 153 |
| | | | 7.3.2.14 | iidcVer | 153 |
| | | | 7.3.2.15 | interfaceType | 153 |
| | | | 7.3.2.16 | ipAddress | 153 |

xii CONTENTS

| | | 7.3.2.17 | isColorCamera |
|-----|--------|-----------|---------------------------|
| | | 7.3.2.18 | macAddress |
| | | 7.3.2.19 | maximumBusSpeed |
| | | 7.3.2.20 | modelName |
| | | 7.3.2.21 | nodeNumber |
| | | 7.3.2.22 | pcieBusSpeed |
| | | 7.3.2.23 | reserved |
| | | 7.3.2.24 | sensorInfo |
| | | 7.3.2.25 | sensorResolution |
| | | 7.3.2.26 | serialNumber |
| | | 7.3.2.27 | subnetMask |
| | | 7.3.2.28 | userDefinedName |
| | | 7.3.2.29 | vendorName |
| | | 7.3.2.30 | xmlURL1 |
| | | 7.3.2.31 | xmlURL2 |
| 7.4 | fc2Car | meraStats | Struct Reference |
| | 7.4.1 | Detailed | Description |
| | 7.4.2 | Field Doo | cumentation |
| | | 7.4.2.1 | cameraCurrents |
| | | 7.4.2.2 | cameraPowerUp |
| | | 7.4.2.3 | cameraVoltages |
| | | 7.4.2.4 | imageCorrupt |
| | | 7.4.2.5 | imageDriverDropped |
| | | 7.4.2.6 | imageDropped |
| | | 7.4.2.7 | imageXmitFailed |
| | | 7.4.2.8 | numCurrents |
| | | 7.4.2.9 | numResendPacketsReceived |
| | | 7.4.2.10 | numResendPacketsRequested |
| | | 7.4.2.11 | numVoltages |
| | | 74040 | portErrors |

CONTENTS xiii

| | | 7.4.2.13 | regReadFailed |
|-----|--------|-------------|-------------------------------|
| | | 7.4.2.14 | regWriteFailed |
| | | 7.4.2.15 | reserved |
| | | 7.4.2.16 | temperature |
| | | 7.4.2.17 | timeSinceBusReset |
| | | 7.4.2.18 | timeSinceInitialization |
| | | 7.4.2.19 | timeStamp |
| 7.5 | fc2Cor | nfig Struct | Reference |
| | 7.5.1 | Detailed | Description |
| | 7.5.2 | Field Doo | cumentation |
| | | 7.5.2.1 | asyncBusSpeed |
| | | 7.5.2.2 | bandwidthAllocation |
| | | 7.5.2.3 | grabMode |
| | | 7.5.2.4 | grabTimeout |
| | | 7.5.2.5 | highPerformanceRetrieveBuffer |
| | | 7.5.2.6 | isochBusSpeed |
| | | 7.5.2.7 | minNumImageNotifications |
| | | 7.5.2.8 | numBuffers |
| | | 7.5.2.9 | numImageNotifications |
| | | 7.5.2.10 | registerTimeout |
| | | 7.5.2.11 | registerTimeoutRetries |
| | | 7.5.2.12 | reserved |
| 7.6 | fc2Cor | nfigROM S | struct Reference |
| | 7.6.1 | Detailed | Description |
| | 7.6.2 | Field Doo | cumentation |
| | | 7.6.2.1 | chipldHi |
| | | 7.6.2.2 | chipldLo |
| | | 7.6.2.3 | nodeVendorld |
| | | 7.6.2.4 | pszKeyword |
| | | 7.6.2.5 | reserved |

xiv CONTENTS

| | | 7.6.2.6 | unitSpecId | 65 |
|-----|--------|------------|----------------------------------|----|
| | | 7.6.2.7 | unitSubSWVer | 65 |
| | | 7.6.2.8 | unitSWVer | 65 |
| | | 7.6.2.9 | vendorUniqueInfo_0 | 65 |
| | | 7.6.2.10 | vendorUniqueInfo_1 | 65 |
| | | 7.6.2.11 | vendorUniqueInfo_2 | 65 |
| | | 7.6.2.12 | vendorUniqueInfo_3 | 66 |
| 7.7 | fc2Eml | oeddedIma | ageInfo Struct Reference | 66 |
| | 7.7.1 | Detailed | Description | 67 |
| | 7.7.2 | Field Doo | cumentation | 67 |
| | | 7.7.2.1 | brightness | 67 |
| | | 7.7.2.2 | exposure | 67 |
| | | 7.7.2.3 | frameCounter | 67 |
| | | 7.7.2.4 | gain | 67 |
| | | 7.7.2.5 | GPIOPinState | 67 |
| | | 7.7.2.6 | ROIPosition | 67 |
| | | 7.7.2.7 | shutter | 68 |
| | | 7.7.2.8 | strobePattern | 68 |
| | | 7.7.2.9 | timestamp | 68 |
| | | 7.7.2.10 | whiteBalance | 68 |
| 7.8 | fc2Eml | oeddedIma | ageInfoProperty Struct Reference | 68 |
| | 7.8.1 | Detailed | Description | 68 |
| | 7.8.2 | Field Doo | cumentation | 68 |
| | | 7.8.2.1 | available | 69 |
| | | 7.8.2.2 | onOff | 69 |
| 7.9 | fc2Eve | ntCallback | Data Struct Reference | 69 |
| | 7.9.1 | Field Doo | cumentation | 69 |
| | | 7.9.1.1 | EventData | 69 |
| | | 7.9.1.2 | EventDataSize | 70 |
| | | 7.9.1.3 | EventID | 70 |

CONTENTS xv

| | | 7.9.1.4 | EventName | 170 |
|------|---------|------------|----------------------------|---------|
| | | 7.9.1.5 | EventTimestamp | 170 |
| | | 7.9.1.6 | EventUserData | 170 |
| | | 7.9.1.7 | EventUserDataSize | 170 |
| 7.10 | fc2Eve | ntOptions | Struct Reference | 171 |
| | 7.10.1 | Detailed | Description | 171 |
| | 7.10.2 | Field Doo | cumentation | 171 |
| | | 7.10.2.1 | EventCallbackFcn | 171 |
| | | 7.10.2.2 | EventName | 171 |
| | | 7.10.2.3 | EventUserData | 171 |
| | | 7.10.2.4 | EventUserDataSize | 172 |
| 7.11 | fc2Forr | nat7Image | eSettings Struct Reference | 172 |
| | 7.11.1 | Detailed | Description | 172 |
| | 7.11.2 | Field Doo | cumentation | 172 |
| | | 7.11.2.1 | height | 172 |
| | | 7.11.2.2 | mode | 173 |
| | | 7.11.2.3 | offsetX | 173 |
| | | 7.11.2.4 | offsetY | 173 |
| | | 7.11.2.5 | pixelFormat | 173 |
| | | 7.11.2.6 | reserved | 173 |
| | | 7.11.2.7 | width | 173 |
| 7.12 | fc2Forr | mat7Info S | Struct Reference | 174 |
| | 7.12.1 | Detailed | Description | 174 |
| | 7.12.2 | Field Doo | cumentation | 174 |
| | | 7.12.2.1 | imageHStepSize | 174 |
| | | 7.12.2.2 | imageVStepSize | 175 |
| | | 7.12.2.3 | maxHeight | 175 |
| | | 7.12.2.4 | maxPacketSize | 175 |
| | | 7.12.2.5 | maxWidth | 175 |
| | | 7.12.2.6 | minPacketSize | 175 |

xvi CONTENTS

| 7.12.2.8 offset/StepSize 17 7.12.2.9 offset/VstepSize 17 7.12.2.10 packetSize 17 7.12.2.11 percentage 17 7.12.2.12 pixelFormatBitField 17 7.12.2.13 reserved 17 7.12.2.14 vendorPixelFormatBitField 17 7.13 fc2Format/PacketInfo Struct Reference 17 7.13.1 Detailed Description 17 7.13.2 Field Documentation 17 7.13.2.1 maxBytesPerPacket 17 7.13.2.2 recommendedBytesPerPacket 17 7.13.2.3 reserved 17 7.13.2.4 unitBytesPerPacket 17 7.14 fc2GigEConfig Struct Reference 17 7.14.1 Detailed Description 17 7.14.2 Field Documentation 17 7.14.2.2 registerTimeout 17 7.14.2.3 registerTimeoutRetries 17 7.15 fc2GigEImageSettings Struct Reference 17 7.15.1 Detailed Description 18 7.15.2.1 height 18 7.15.2.2 offsetX 18 7.15.2.3 offsetY 18 7.15.2.4 pixelFormat 18 7.15.2.4 pixelFormat | | 7.12.2.7 | mode | 175 |
|--|----------|---------------|-----------------------------|---------|
| 7.12.2.10 packetSize 176 7.12.2.11 percentage 177 7.12.2.12 pixelFormatBitField 177 7.12.2.13 reserved 177 7.12.2.14 vendorPixelFormatBitField 177 7.13 fc2Format7PacketInfo Struct Reference 177 7.13.1 Detailed Description 177 7.13.2 Field Documentation 177 7.13.2.1 maxBytesPerPacket 178 7.13.2.2 recommendedBytesPerPacket 178 7.13.2.3 reserved 178 7.13.2.4 unitBytesPerPacket 178 7.14.1 Detailed Description 178 7.14.2 Field Documentation 178 7.14.2.1 enablePacketResend 178 7.14.2.3 registerTimeout 178 7.14.2.4 reserved 178 7.15.1 Detailed Description 188 7.15.2 Field Documentation 180 7.15.2 Field Documentation 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetY 181 7.15.2.3 offsetY 181 | | 7.12.2.8 | offsetHStepSize | 176 |
| 7.12.2.11 percentage 176 7.12.2.12 pixelFormatBitField 177 7.12.2.13 reserved 176 7.12.2.14 vendorPixelFormatBitField 177 7.13 fc2Format7PacketInfo Struct Reference 177 7.13.1 Detailed Description 177 7.13.2 Field Documentation 177 7.13.2.1 maxBytesPerPacket 177 7.13.2.2 recommendedBytesPerPacket 176 7.13.2.3 reserved 177 7.14 fc2GigEConfig Struct Reference 178 7.14.1 Detailed Description 178 7.14.2 Field Documentation 178 7.14.2.1 enablePacketResend 178 7.14.2.2 registerTimeout 178 7.14.2.3 registerTimeoutRetries 178 7.15.1 Detailed Description 188 7.15.2 Field Documentation 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 181 | | 7.12.2.9 | offsetVStepSize | 176 |
| 7.12.2.12 pixelFormatBitField 176 7.12.2.13 reserved 176 7.12.2.14 vendorPixelFormatBitField 177 7.13 fc2Format7PacketInfo Struct Reference 177 7.13.1 Detailed Description 177 7.13.2 Field Documentation 177 7.13.2.1 maxBytesPerPacket 176 7.13.2.2 recommendedBytesPerPacket 176 7.13.2.3 reserved 176 7.13.2.4 unitBytesPerPacket 177 7.14 to2GigEConfig Struct Reference 178 7.14.1 Detailed Description 176 7.14.2 Field Documentation 178 7.14.2.1 enablePacketResend 178 7.14.2.2 registerTimeout 178 7.14.2.4 reserved 178 7.15 fc2GigEImageSettings Struct Reference 178 7.15.1 Detailed Description 186 7.15.2 field Documentation 186 7.15.2.1 height 186 7.15.2.2 offsetX 186 7.15.2.3 offsetY 186 | | 7.12.2.10 | 0 packetSize | 176 |
| 7.12.2.13 reserved 176 7.12.2.14 vendorPixelFormatBitField 177 7.13 fc2Format7PacketInfo Struct Reference 177 7.13.1 Detailed Description 177 7.13.2 Field Documentation 177 7.13.2.1 maxBytesPerPacket 177 7.13.2.2 recommendedBytesPerPacket 176 7.13.2.3 reserved 176 7.13.2.4 unitBytesPerPacket 176 7.14 fc2GigEConfig Struct Reference 176 7.14.1 Detailed Description 176 7.14.2 Field Documentation 176 7.14.2.1 enablePacketResend 177 7.14.2.2 registerTimeout 178 7.14.2.3 registerTimeoutRetries 178 7.15 fc2GigEImageSettings Struct Reference 178 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.12.2.11 | 1 percentage | 176 |
| 7.12.2.14 vendorPixelFormatBitField 17. 7.13 fc2Format7PacketInfo Struct Reference 17. 7.13.1 Detailed Description 17. 7.13.2 Field Documentation 17. 7.13.2.1 maxBytesPerPacket 17. 7.13.2.2 recommendedBytesPerPacket 17. 7.13.2.3 reserved 17. 7.13.2.4 unitBytesPerPacket 17. 7.14 fc2GigEConfig Struct Reference 17. 7.14.1 Detailed Description 17. 7.14.2 Field Documentation 17. 7.14.2.1 enablePacketResend 17. 7.14.2.2 registerTimeout 17. 7.14.2.3 registerTimeoutRetries 17. 7.15 fc2GigEImageSettings Struct Reference 17. 7.15.1 Detailed Description 18. 7.15.2.1 height 18. 7.15.2.2 offsetX 18. 7.15.2.3 offsetY 18. 7.15.2.3 offsetY 18. | | 7.12.2.12 | 2 pixelFormatBitField | 176 |
| 7.13 fc2Format7PacketInfo Struct Reference 17. 7.13.1 Detailed Description 17. 7.13.2 Field Documentation 17. 7.13.2.1 maxBytesPerPacket 17. 7.13.2.2 recommendedBytesPerPacket 17. 7.13.2.3 reserved 17. 7.13.2.4 unitBytesPerPacket 17. 7.14 fc2GigEConfig Struct Reference 17. 7.14.1 Detailed Description 17. 7.14.2 Field Documentation 17. 7.14.2.1 enablePacketResend 17. 7.14.2.2 registerTimeout 17. 7.14.2.3 registerTimeoutRetries 17. 7.15 fc2GigEImageSettings Struct Reference 17. 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.12.2.13 | 3 reserved | 176 |
| 7.13.1 Detailed Description 17. 7.13.2 Field Documentation 17. 7.13.2.1 maxBytesPerPacket 17. 7.13.2.2 recommendedBytesPerPacket 17. 7.13.2.3 reserved 17. 7.13.2.4 unitBytesPerPacket 17. 7.14 fc2GigEConfig Struct Reference 17. 7.14.1 Detailed Description 17. 7.14.2 Field Documentation 17. 7.14.2.1 enablePacketResend 17. 7.14.2.2 registerTimeout 17. 7.14.2.3 registerTimeoutRetries 17. 7.14.2.4 reserved 17. 7.15 fc2GigEImageSettings Struct Reference 17. 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.12.2.14 | 4 vendorPixelFormatBitField | 177 |
| 7.13.2 Field Documentation 17. 7.13.2.1 maxBytesPerPacket 17. 7.13.2.2 recommendedBytesPerPacket 17. 7.13.2.3 reserved 17. 7.13.2.4 unltBytesPerPacket 17. 7.14 fc2GigEConfig Struct Reference 17. 7.14.1 Detailed Description 17. 7.14.2 Field Documentation 17. 7.14.2.1 enablePacketResend 17. 7.14.2.2 registerTimeout 17. 7.14.2.3 registerTimeoutRetries 17. 7.14.2.4 reserved 17. 7.15.1 Detailed Description 18. 7.15.2 Field Documentation 18. 7.15.2.1 height 18. 7.15.2.2 offsetX 18. 7.15.2.3 offsetY 18. | 7.13 fc2 | Format7Packe | etInfo Struct Reference | 177 |
| 7.13.2.1 maxBytesPerPacket 17. 7.13.2.2 recommendedBytesPerPacket 17. 7.13.2.3 reserved 17. 7.13.2.4 unitBytesPerPacket 17. 7.14 fc2GigEConfig Struct Reference 17. 7.14.1 Detailed Description 17. 7.14.2 Field Documentation 17. 7.14.2.1 enablePacketResend 17. 7.14.2.2 registerTimeout 17. 7.14.2.3 registerTimeoutRetries 17. 7.14.2.4 reserved 17. 7.15 fc2GigEImageSettings Struct Reference 17. 7.15.1 Detailed Description 180. 7.15.2 Field Documentation 180. 7.15.2.2 offsetX 180. 7.15.2.3 offsetY 180. | 7.1 | 3.1 Detailed | Description | 177 |
| 7.13.2.2 recommendedBytesPerPacket 176 7.13.2.3 reserved 176 7.13.2.4 unitBytesPerPacket 176 7.14 fc2GigEConfig Struct Reference 176 7.14.1 Detailed Description 176 7.14.2 Field Documentation 176 7.14.2.1 enablePacketResend 176 7.14.2.2 registerTimeout 176 7.14.2.3 registerTimeoutRetries 176 7.14.2.4 reserved 176 7.15 fc2GigEImageSettings Struct Reference 176 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | 7.1 | 3.2 Field Doo | cumentation | 177 |
| 7.13.2.3 reserved 176 7.13.2.4 unitBytesPerPacket 176 7.14 fc2GigEConfig Struct Reference 176 7.14.1 Detailed Description 176 7.14.2 Field Documentation 176 7.14.2.1 enablePacketResend 176 7.14.2.2 registerTimeout 176 7.14.2.3 registerTimeoutRetries 176 7.14.2.4 reserved 178 7.15 fc2GigEImageSettings Struct Reference 176 7.15.1 Detailed Description 186 7.15.2 Field Documentation 186 7.15.2.1 height 186 7.15.2.2 offsetX 186 7.15.2.3 offsetY 186 | | 7.13.2.1 | maxBytesPerPacket | 177 |
| 7.13.2.4 unitBytesPerPacket 176 7.14 fc2GigEConfig Struct Reference 176 7.14.1 Detailed Description 176 7.14.2 Field Documentation 175 7.14.2.1 enablePacketResend 175 7.14.2.2 registerTimeout 175 7.14.2.3 registerTimeoutRetries 175 7.14.2.4 reserved 175 7.15 fc2GigEImageSettings Struct Reference 175 7.15.1 Detailed Description 186 7.15.2.1 height 186 7.15.2.2 offsetX 186 7.15.2.3 offsetY 186 | | 7.13.2.2 | recommendedBytesPerPacket | 178 |
| 7.14 fc2GigEConfig Struct Reference 176 7.14.1 Detailed Description 176 7.14.2 Field Documentation 178 7.14.2.1 enablePacketResend 178 7.14.2.2 registerTimeout 178 7.14.2.3 registerTimeoutRetries 178 7.14.2.4 reserved 178 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.13.2.3 | reserved | 178 |
| 7.14.1 Detailed Description 178 7.14.2 Field Documentation 178 7.14.2.1 enablePacketResend 178 7.14.2.2 registerTimeout 178 7.14.2.3 registerTimeoutRetries 178 7.14.2.4 reserved 178 7.15 fc2GigEImageSettings Struct Reference 178 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.13.2.4 | unitBytesPerPacket | 178 |
| 7.14.2 Field Documentation 175 7.14.2.1 enablePacketResend 175 7.14.2.2 registerTimeout 175 7.14.2.3 registerTimeoutRetries 175 7.14.2.4 reserved 175 7.15 fc2GigEImageSettings Struct Reference 175 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | 7.14 fc2 | GigEConfig S | truct Reference | 178 |
| 7.14.2.1 enablePacketResend 179 7.14.2.2 registerTimeout 179 7.14.2.3 registerTimeoutRetries 179 7.14.2.4 reserved 179 7.15 fc2GigEImageSettings Struct Reference 179 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | 7.1 | 4.1 Detailed | Description | 178 |
| 7.14.2.2 registerTimeout 175 7.14.2.3 registerTimeoutRetries 175 7.14.2.4 reserved 175 7.15 fc2GigEImageSettings Struct Reference 175 7.15.1 Detailed Description 186 7.15.2 Field Documentation 186 7.15.2.1 height 186 7.15.2.2 offsetX 186 7.15.2.3 offsetY 186 | 7.1 | 4.2 Field Doo | cumentation | 179 |
| 7.14.2.3 registerTimeoutRetries | | 7.14.2.1 | enablePacketResend | 179 |
| 7.14.2.4 reserved 179 7.15 fc2GigEImageSettings Struct Reference 179 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.14.2.2 | registerTimeout | 179 |
| 7.15 fc2GigEImageSettings Struct Reference 179 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.14.2.3 | registerTimeoutRetries | 179 |
| 7.15.1 Detailed Description 180 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | | 7.14.2.4 | reserved | 179 |
| 7.15.2 Field Documentation 180 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | 7.15 fc2 | GigElmageSe | ettings Struct Reference | 179 |
| 7.15.2.1 height 180 7.15.2.2 offsetX 180 7.15.2.3 offsetY 180 | 7.1 | 5.1 Detailed | Description | 180 |
| 7.15.2.2 offsetX | 7.1 | 5.2 Field Doo | cumentation | 180 |
| 7.15.2.3 offsetY | | 7.15.2.1 | height | 180 |
| | | 7.15.2.2 | offsetX | 180 |
| 7.15.2.4 pixelFormat | | 7.15.2.3 | offsetY | 180 |
| | | 7.15.2.4 | pixelFormat | 181 |
| 7.15.2.5 reserved | | 7.15.2.5 | reserved | 181 |

CONTENTS xvii

| | | 7.15.2.6 | width | | | | | | | | | 181 |
|------|---------|-----------|---------------|------------|----------|---|------|------|------|------|------|---------|
| 7.16 | fc2GigI | ∃lmageSe | ttingsInfo St | ruct Refe | erence | | | | | | | 181 |
| | 7.16.1 | Detailed | Description | | | | | | | | | 182 |
| | 7.16.2 | Field Doo | cumentation | | | | | | | | | 182 |
| | | 7.16.2.1 | imageHSte | pSize . | | | | | | | | 182 |
| | | 7.16.2.2 | imageVSte | pSize . | | | | | | | | 182 |
| | | 7.16.2.3 | maxHeight | | | | | | | | | 182 |
| | | 7.16.2.4 | maxWidth | | | | | | | | | 182 |
| | | 7.16.2.5 | offsetHSte | pSize . | | | | | | | | 182 |
| | | 7.16.2.6 | offsetVSte | oSize . | | | | | | | | 183 |
| | | 7.16.2.7 | pixelForma | ıtBitField | ١ | | | | | | | 183 |
| | | 7.16.2.8 | reserved | | | | | | | | | 183 |
| | | 7.16.2.9 | vendorPixe | IFormat | BitField | d | | | | | | 183 |
| 7.17 | fc2GigI | EProperty | Struct Refer | ence . | | | | | | | | 183 |
| | 7.17.1 | Detailed | Description | | | | | | | | | 184 |
| | 7.17.2 | Field Doo | cumentation | | | | | | | | | 184 |
| | | 7.17.2.1 | isReadable | · | | | | | | | | 184 |
| | | 7.17.2.2 | isWritable | | | | | | | | | 184 |
| | | 7.17.2.3 | max | | | | | | | | | 184 |
| | | 7.17.2.4 | min | | | | | | | | | 184 |
| | | 7.17.2.5 | propType | | | | | | | | | 184 |
| | | 7.17.2.6 | reserved | | | | | | | | | 185 |
| | | 7.17.2.7 | value | | | | | | | | | 185 |
| 7.18 | fc2GigI | EStreamC | hannel Strud | ct Refere | ence. | | | | | | | 185 |
| | 7.18.1 | Detailed | Description | | | | | | | | | 186 |
| | 7.18.2 | Field Doo | cumentation | | | | | | | | | 186 |
| | | 7.18.2.1 | destination | lpAddre: | SS | | | | | | | 186 |
| | | 7.18.2.2 | doNotFrag | ment . | | | | | | | | 186 |
| | | 7.18.2.3 | hostPort | | | | | | | | | 186 |
| | | 7.18.2.4 | interPacke | tDelay . | | | | | | | | 186 |
| | | | | | | | | | | | | |

xviii CONTENTS

| | | 7.18.2.5 | networkInterfaceIndex | | | | | 186 |
|--------|---------|-------------|-----------------------|------|------|------|------|---------|
| | | 7.18.2.6 | packetSize | | | | | 187 |
| | | 7.18.2.7 | reserved | | | | | 187 |
| | | 7.18.2.8 | sourcePort | | | | | 187 |
| 7.19 f | fc2H26 | 4Option S | ruct Reference | | | | | 187 |
| 7 | 7.19.1 | Detailed | Description | | | | | 187 |
| 7 | 7.19.2 | Field Doo | umentation | | | | | 188 |
| | | 7.19.2.1 | bitrate | | | | | 188 |
| | | 7.19.2.2 | frameRate | | | | | 188 |
| | | 7.19.2.3 | height | | | | | 188 |
| | | 7.19.2.4 | reserved | | | | | 188 |
| | | 7.19.2.5 | width | | | | | 188 |
| 7.20 f | fc2lmaç | ge Struct F | eference | | | | | 189 |
| 7 | 7.20.1 | Field Doo | umentation | | | | | 189 |
| | | 7.20.1.1 | bayerFormat | | | | | 189 |
| | | 7.20.1.2 | cols | | | | | 189 |
| | | 7.20.1.3 | dataSize | | | | | 189 |
| | | 7.20.1.4 | format | | | | | 189 |
| | | 7.20.1.5 | imageImpl | | | | | 189 |
| | | 7.20.1.6 | pData | | | | | 190 |
| | | 7.20.1.7 | receivedDataSize | | | | | 190 |
| | | 7.20.1.8 | rows | | | | | 190 |
| | | 7.20.1.9 | stride | | | | | 190 |
| 7.21 f | fc2lmaç | geMetadat | a Struct Reference | | | | | 190 |
| 7 | 7.21.1 | Detailed | Description | | | | | 191 |
| 7 | 7.21.2 | Field Doo | umentation | | | | | 191 |
| | | 7.21.2.1 | embeddedBrightness | | | | | 191 |
| | | 7.21.2.2 | embeddedExposure | | | | | 191 |
| | | 7.21.2.3 | embeddedFrameCounter | | | | | 191 |
| | | 7.21.2.4 | embeddedGain | | | | | 191 |
| | | | | | | | | |

CONTENTS xix

| | 7.21.2.5 embeddedGPIOPinState |
|--------------|-------------------------------------|
| | 7.21.2.6 embeddedROIPosition |
| | 7.21.2.7 embeddedShutter |
| | 7.21.2.8 embeddedStrobePattern |
| | 7.21.2.9 embeddedTimeStamp |
| | 7.21.2.10 embeddedWhiteBalance |
| | 7.21.2.11 reserved |
| 7.22 fc2Inte | ernalContext Struct Reference |
| 7.22.1 | Field Documentation |
| | 7.22.1.1 pBusMgr |
| | 7.22.1.2 pCamera |
| 7.23 fc2Inte | ernalGuiContext Struct Reference |
| 7.23.1 | Field Documentation |
| | 7.23.1.1 pCameraControlDlg |
| | 7.23.1.2 pCameraSelectionDlg |
| 7.24 fc2Inte | ernallmageCallback Struct Reference |
| 7.24.1 | Field Documentation |
| | 7.24.1.1 pCallback |
| | 7.24.1.2 pCallbackData |
| 7.25 fc2IPA | address Struct Reference |
| 7.25.1 | Detailed Description |
| 7.25.2 | Field Documentation |
| | 7.25.2.1 octets |
| 7.26 fc2JP | EGOption Struct Reference |
| 7.26.1 | Detailed Description |
| 7.26.2 | Field Documentation |
| | 7.26.2.1 progressive |
| | 7.26.2.2 quality |
| | 7.26.2.3 reserved |
| 7.27 fc2JP | G2Option Struct Reference |

CONTENTS

| | 7.27.1 | Detailed Description | 97 |
|------|--------|---------------------------|-------------|
| | 7.27.2 | Field Documentation | 97 |
| | | 7.27.2.1 quality | 97 |
| | | 7.27.2.2 reserved | 97 |
| 7.28 | fc2LUT | Data Struct Reference | 97 |
| | 7.28.1 | Detailed Description | 98 |
| | 7.28.2 | Field Documentation | 98 |
| | | 7.28.2.1 enabled | 98 |
| | | 7.28.2.2 inputBitDepth | 98 |
| | | 7.28.2.3 numBanks | 98 |
| | | 7.28.2.4 numChannels | 98 |
| | | 7.28.2.5 numEntries | 98 |
| | | 7.28.2.6 outputBitDepth | 99 |
| | | 7.28.2.7 reserved | 99 |
| | | 7.28.2.8 supported | 99 |
| 7.29 | fc2MA0 | CAddress Struct Reference | 99 |
| | 7.29.1 | Detailed Description | 99 |
| | 7.29.2 | Field Documentation | 99 |
| | | 7.29.2.1 octets | 200 |
| 7.30 | fc2MJF | PGOption Struct Reference | 200 |
| | 7.30.1 | Detailed Description | 200 |
| | 7.30.2 | Field Documentation | 200 |
| | | 7.30.2.1 frameRate | 200 |
| | | 7.30.2.2 quality | 200 |
| | | 7.30.2.3 reserved | 201 |
| 7.31 | fc2PGN | MOption Struct Reference | <u>2</u> 01 |
| | 7.31.1 | Detailed Description | 201 |
| | 7.31.2 | Field Documentation | 201 |
| | | 7.31.2.1 binaryFile | 201 |
| | | 7.31.2.2 reserved | 201 |

CONTENTS xxi

| 7.32 | fc2PGF | Guid Struct Reference | 202 |
|------|---------|----------------------------|-----|
| | 7.32.1 | Detailed Description | 202 |
| | 7.32.2 | Field Documentation | 202 |
| | | 7.32.2.1 value | 202 |
| 7.33 | fc2PNG | Option Struct Reference | 202 |
| | 7.33.1 | Detailed Description | 202 |
| | 7.33.2 | Field Documentation | 203 |
| | | 7.33.2.1 compressionLevel | 203 |
| | | 7.33.2.2 interlaced | 203 |
| | | 7.33.2.3 reserved | 203 |
| 7.34 | fc2PPN | Option Struct Reference | 203 |
| | 7.34.1 | Detailed Description | 203 |
| | 7.34.2 | Field Documentation | 204 |
| | | 7.34.2.1 binaryFile | 204 |
| | | 7.34.2.2 reserved | 204 |
| 7.35 | fc2Stro | peControl Struct Reference | 204 |
| | 7.35.1 | Detailed Description | 204 |
| | 7.35.2 | Field Documentation | 205 |
| | | 7.35.2.1 delay | 205 |
| | | 7.35.2.2 duration | 205 |
| | | 7.35.2.3 onOff | 205 |
| | | 7.35.2.4 polarity | 205 |
| | | 7.35.2.5 reserved | 205 |
| | | 7.35.2.6 source | 206 |
| 7.36 | fc2Stro | peInfo Struct Reference | 206 |
| | 7.36.1 | Detailed Description | 206 |
| | 7.36.2 | Field Documentation | 206 |
| | | 7.36.2.1 maxValue | 206 |
| | | 7.36.2.2 minValue | 207 |
| | | 7.36.2.3 onOffSupported | 207 |

xxii CONTENTS

| | 7.36.2.4 polaritySupported |)7 |
|-------------|----------------------------|----|
| | 7.36.2.5 present |)7 |
| | 7.36.2.6 readOutSupported |)7 |
| | 7.36.2.7 reserved |)7 |
| | 7.36.2.8 source | 8(|
| 7.37 fc2Sys | temInfo Struct Reference | 8(|
| 7.37.1 | Detailed Description | 8(|
| 7.37.2 | Field Documentation |)9 |
| | 7.37.2.1 byteOrder |)9 |
| | 7.37.2.2 cpuDescription |)9 |
| | 7.37.2.3 driverList |)9 |
| | 7.37.2.4 gpuDescription |)9 |
| | 7.37.2.5 libraryList |)9 |
| | 7.37.2.6 numCpuCores | 0 |
| | 7.37.2.7 osDescription | 0 |
| | 7.37.2.8 osType | 0 |
| | 7.37.2.9 reserved | 0 |
| | 7.37.2.10 screenHeight | 0 |
| | 7.37.2.11 screenWidth | 0 |
| | 7.37.2.12 sysMemSize | 1 |
| 7.38 fc2TIF | FOption Struct Reference | 1 |
| 7.38.1 | Detailed Description | 1 |
| 7.38.2 | Field Documentation | 1 |
| | 7.38.2.1 compression | 1 |
| | 7.38.2.2 reserved | 1 |
| 7.39 fc2Tim | eStamp Struct Reference | 2 |
| 7.39.1 | Detailed Description | 2 |
| 7.39.2 | Field Documentation | 2 |
| | 7.39.2.1 cycleCount | 2 |
| | 7.39.2.2 cycleOffset | 2 |

CONTENTS xxiii

| | 7.39.2.3 | cycleSeconds | | | | | | | 213 |
|----------------|------------|-----------------|----------|------|------|------|------|------|-----|
| | 7.39.2.4 | microSeconds | 3 | | | | | | 213 |
| | 7.39.2.5 | reserved | | | | | | | 213 |
| | 7.39.2.6 | seconds | | | | | | | 213 |
| 7.40 fc2Trigge | erDelay S | truct Referenc | e | | | | | | 213 |
| 7.40.1 | Detailed [| Description . | | | | | | | 214 |
| 7.40.2 | Field Doc | umentation . | | | | | | | 214 |
| | 7.40.2.1 | absControl . | | | | | | | 214 |
| | 7.40.2.2 | absValue | | | | | | | 215 |
| | 7.40.2.3 | autoManualM | ode | | | | | | 215 |
| | 7.40.2.4 | onePush | | | | | | | 215 |
| | 7.40.2.5 | onOff | | | | | | | 215 |
| | 7.40.2.6 | present | | | | | | | 215 |
| | 7.40.2.7 | reserved | | | | | | | 215 |
| | 7.40.2.8 | type | | | | | | | 216 |
| | 7.40.2.9 | valueA | | | | | | | 216 |
| | 7.40.2.10 | valueB | | | | | | | 216 |
| 7.41 fc2Trigge | erDelayIn | fo Struct Refer | ence | | | | | | 216 |
| 7.41.1 | Detailed [| Description . | | | | | | | 217 |
| 7.41.2 | Field Doc | umentation . | | | | | | | 217 |
| | 7.41.2.1 | absMax | | | | | | | 217 |
| | 7.41.2.2 | absMin | | | | | | | 217 |
| | 7.41.2.3 | absValSuppor | ted | | | | | | 217 |
| | 7.41.2.4 | autoSupporte | d | | | | | | 218 |
| | 7.41.2.5 | manualSuppo | rted | | | | | | 218 |
| | 7.41.2.6 | max | | | | | | | 218 |
| | 7.41.2.7 | min | | | | | | | 218 |
| | 7.41.2.8 | onePushSupp | orted . | | | | | | 218 |
| | 7.41.2.9 | onOffSupport | ed | | | | | | 218 |
| | 7.41.2.10 | present | | | | | | | 219 |

xxiv CONTENTS

| | 7.41.2.11 pUnitAbbr | 219 |
|--------------|-----------------------------------|-----|
| | 7.41.2.12 pUnits | 219 |
| | 7.41.2.13 readOutSupported | 219 |
| | 7.41.2.14 reserved | 219 |
| | 7.41.2.15 type | 219 |
| 7.42 fc2Triç | ggerMode Struct Reference | 220 |
| 7.42.1 | Detailed Description | 220 |
| 7.42.2 | Prield Documentation | 220 |
| | 7.42.2.1 mode | 220 |
| | 7.42.2.2 onOff | 220 |
| | 7.42.2.3 parameter | 221 |
| | 7.42.2.4 polarity | 221 |
| | 7.42.2.5 reserved | 221 |
| | 7.42.2.6 source | 221 |
| 7.43 fc2Triç | ggerModeInfo Struct Reference | 221 |
| 7.43.1 | Detailed Description | 222 |
| 7.43.2 | Prield Documentation | 222 |
| | 7.43.2.1 modeMask | 222 |
| | 7.43.2.2 onOffSupported | 222 |
| | 7.43.2.3 polaritySupported | 223 |
| | 7.43.2.4 present | 223 |
| | 7.43.2.5 readOutSupported | 223 |
| | 7.43.2.6 reserved | 223 |
| | 7.43.2.7 softwareTriggerSupported | 223 |
| | 7.43.2.8 sourceMask | 223 |
| | 7.43.2.9 valueReadable | 224 |
| 7.44 fc2Vei | rsion Struct Reference | 224 |
| 7.44.1 | Detailed Description | 224 |
| 7.44.2 | Prield Documentation | 224 |
| | 7.44.2.1 build | 224 |
| | 7.44.2.2 major | 225 |
| | 7.44.2.3 minor | 225 |
| | 7.44.2.4 type | 225 |

CONTENTS xxv

| 8 | File | Docum | entation | | 227 |
|---|------|--------|------------|--------------------------|-----|
| | 8.1 | FlyCap | oture2_C.h | File Reference | 227 |
| | | 8.1.1 | Function | Documentation | 236 |
| | | | 8.1.1.1 | fc2CreateContext() | 236 |
| | | | 8.1.1.2 | fc2CreateGigEContext() | 237 |
| | | | 8.1.1.3 | fc2DeregisterAllEvents() | 237 |
| | | | 8.1.1.4 | fc2DeregisterEvent() | 237 |
| | | | 8.1.1.5 | fc2DestroyContext() | 238 |
| | | | 8.1.1.6 | fc2GetCycleTime() | 238 |
| | | | 8.1.1.7 | fc2GetStats() | 239 |
| | | | 8.1.1.8 | fc2RegisterAllEvents() | 239 |
| | | | 8.1.1.9 | fc2RegisterEvent() | 240 |
| | | | 8.1.1.10 | ResetStats() | 240 |
| | 8.2 | FlyCap | oture2Defs | _C.h File Reference | 240 |
| | | 8.2.1 | Enumera | ttion Type Documentation | 248 |
| | | | 8.2.1.1 | fc2ByteOrder | 248 |
| | | | 8.2.1.2 | fc2NodeType | 249 |
| | | | 8.2.1.3 | fc2OSType | 249 |
| | | | 8.2.1.4 | fc2PortType | 249 |
| | | | 8.2.1.5 | fc2StatisticsChannel | 250 |
| | 8.3 | FlyCap | oture2GUI_ | _C.h File Reference | 250 |
| | | 8.3.1 | Function | Documentation | 251 |
| | | | 8.3.1.1 | fc2CreateGUIContext() | 251 |
| | | | 8.3.1.2 | fc2DestroyGUIContext() | 251 |
| | | | 8.3.1.3 | fc2Disonnect() | 252 |
| | | | 8.3.1.4 | fc2GUIConnect() | 252 |
| | | | 8.3.1.5 | fc2GUIDisconnect() | 253 |
| | | | 8.3.1.6 | fc2Hide() | 253 |
| | | | 8.3.1.7 | fc2IsVisible() | 253 |
| | | | 8.3.1.8 | fc2Show() | 254 |
| | | | | | |

xxvi CONTENTS

| | | 8.3.1.9 | fc2ShowModal() | 254 |
|------|---------|------------|--|-----|
| 8.4 | FlyCap | ture2Inter | rnal_C.h File Reference | 255 |
| | 8.4.1 | Function | Documentation | 255 |
| | | 8.4.1.1 | IsContextValid() | 255 |
| | | 8.4.1.2 | IsGuiContextValid() | 255 |
| | | 8.4.1.3 | SyncCppImageToStruct() | 256 |
| 8.5 | FlyCap | ture2Platf | form_C.h File Reference | 256 |
| | 8.5.1 | Macro De | efinition Documentation | 256 |
| | | 8.5.1.1 | FLYCAPTURE2_C_API | 256 |
| | | 8.5.1.2 | FLYCAPTURE2_C_CALL_CONVEN | 256 |
| 8.6 | FlyCap | ture2Priva | ate_C.h File Reference | 257 |
| | 8.6.1 | Function | Documentation | 257 |
| | | 8.6.1.1 | GetInternal() | 257 |
| 8.7 | FlyCap | ture2Vide | o_C.h File Reference | 257 |
| 8.8 | FlyCap | ture2Vide | oDefs_C.h File Reference | 258 |
| 8.9 | Licensi | ng.dox Fil | e Reference | 259 |
| 8.10 | MultiSy | ncLibrary | _C.h File Reference | 259 |
| | 8.10.1 | Function | Documentation | 260 |
| | | 8.10.1.1 | syncCreateContext() | 260 |
| | | 8.10.1.2 | syncDestroyContext() | 260 |
| | | 8.10.1.3 | syncDisableCrossPCSynchronization() | 260 |
| | | 8.10.1.4 | syncEnableCrossPCSynchronization() | 261 |
| | | 8.10.1.5 | syncGetStatus() | 261 |
| | | 8.10.1.6 | syncGetTimeSinceSynced() | 261 |
| | | 8.10.1.7 | syncIsTimingBusConnected() | 263 |
| | | 8.10.1.8 | syncQueryCrossPCSynchronizationSetting() | 263 |
| | | 8.10.1.9 | syncRescanMasterTimingBus() | 263 |
| | | 8.10.1.10 | O syncStart() | 265 |
| | | 8.10.1.11 | 1 syncStop() | 265 |
| 8.11 | MultiSy | ncLibrary | Defs_C.h File Reference | 266 |

CONTENTS xxvii

| 8.11.1 | Macro De | efinition Documentation | | | | | | 267 |
|-------------|-------------|---------------------------|----------|--------|----|------|------|-----------|
| | 8.11.1.1 | FALSE | | | | | | 267 |
| | 8.11.1.2 | FULL_32BIT_VALUE | | | | | | 267 |
| | 8.11.1.3 | MAX_STRING_LENGT | н | | | | | 267 |
| | 8.11.1.4 | TRUE | | | | | | 267 |
| 8.11.2 | 2 Typedef I | Documentation | | | | | | 268 |
| | 8.11.2.1 | BOOL | | | | | | 268 |
| | 8.11.2.2 | syncContext | | | | | | 268 |
| 8.11.3 | 3 Enumera | tion Type Documentation | | | | | | 268 |
| | 8.11.3.1 | syncError | | | | | | 268 |
| | 8.11.3.2 | syncMessage | | | | | | 268 |
| 8.12 MultiS | SyncLibrary | Platform_C.h File Referer | nce | | | | | 269 |
| 8.12.1 | Macro De | efinition Documentation | | | | | | 269 |
| | 8.12.1.1 | MULTISYNCLIBRARY_ | _C_API . | | | | | 269 |
| | 8.12.1.2 | MULTISYNCLIBRARY_ | _C_CALL | _CONVI | ΞN | | | 269 |
| | | | | | | | | . |
| Index | | | | | | | | 271 |

Chapter 1

Software Licensing Information

Table 1.1 License table

| Component | License |
|-------------|---|
| FlyCapture2 | Copyright © 2017 FLIR Integrated Imaging Solutions, Inc. All Rights Reserved. This software is the confidential and proprietary information of FLIR Integrated Imaging Solutions, Inc. (" Confidential Information"). You shall not disclose such Confidential Information and shall use it only in accordance with the terms of the license agreement you entered into with FLIR Integrated Imaging Solutions, Inc. (FLIR). FLIR MAKES NO REPRESENTATIONS OR WARRANTIES ABOUT THE SUITABILITY OF THE SOFTWARE, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PCURPOSE, OR NON-INFRINGEMENT. FLIR SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. |
| AdapterList | The Code Project Open License (CPOL) http://www.codeproject.← com/info/cpoll0.aspx |
| Boost | Boost Software License http://www.boost.org/users/license.html |
| FFMPEG | LGPv2.1 License https://www.ffmpeg.org/legal.html |
| FreeImage | Freelmage public license http://freeimage.sourceforge.← net/freeimage-license.txt |
| GTK | LGPv2.1 License http://www.gnu.org/licenses/old-licenses/lgpl-2.← 1.txt |
| Libusb | LGPLv2.1 License http://www.gnu.org/licenses/old-licenses/lgpl-2.← 1.txt |
| Libraw1394 | LGPLv2.0 License http://www.gnu.org/licenses/old-licenses/lgpl-2.↔ 0.txt |

Chapter 2

Deprecated List

Global fc2Disonnect (fc2GuiContext context) __attribute__((deprecated))

This method is deprecated and will be removed in a future FlyCapture2 release. Please use fc2GUIDisconnect instead.

Deprecated List

Chapter 3

Module Index

3.1 Modules

Here is a list of all modules:

| Bus Manager Operation | 11 |
|--|----|
| Connection and Image Retrieval | 25 |
| Information and Properties | 34 |
| General Purpose Input / Output | 38 |
| Trigger | 41 |
| Strobe | 48 |
| Look Up Table | 51 |
| Memory Channels | 56 |
| Register Operation | 60 |
| DCAM Formats | 64 |
| | 66 |
| GVCP Register Operation | 69 |
| GigE property manipulation | 73 |
| GigE image settings | 75 |
| GigE image binning settings | 80 |
| - 9 - 9 9 | 82 |
| | 85 |
| ge claiment of the control of the co | 95 |
| TopologyNode Operation | 03 |
| Utilities | |
| TypeDefs | 15 |
| Enumerations | |
| GigE specific enumerations | |
| Structures | 34 |
| GigE specific structures | 36 |
| IIDC specific structures | 37 |
| Image saving structures | 38 |
| Video saving structures | 46 |
| Video Recording Operation | 41 |

6 Module Index

Chapter 4

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

| fc2AVIOption | |
|---|------|
| Options for saving AVI files | 147 |
| fc2BMPOption | |
| Options for saving Bitmap image | 148 |
| fc2CameraInfo | |
| Camera information | 149 |
| fc2CameraStats | |
| Camera diagnostic information | 156 |
| fc2Config | |
| Configuration for a camera | 159 |
| fc2ConfigROM | |
| Camera configuration ROM | 163 |
| fc2EmbeddedImageInfo | |
| Properties of the possible embedded image information | 166 |
| fc2EmbeddedImageInfoProperty | |
| Properties of a single embedded image info property | 168 |
| fc2EventCallbackData | 169 |
| fc2EventOptions | |
| Options for enabling device event registration | 171 |
| fc2Format7ImageSettings | 470 |
| Format 7 image settings | 172 |
| fc2Format7Info | 474 |
| Format 7 information for a single mode | 174 |
| fc2Format7PacketInfo | 4 77 |
| Format 7 packet information | 177 |
| fc2GigEConfig | 470 |
| Configuration for a GigE camera | 178 |
| fc2GigEImageSettings | 170 |
| Image settings for a GigE camera | 179 |
| fc2GigEImageSettingsInfo | 101 |
| Format 7 information for a single mode | 181 |
| fc2GigEProperty A GigE property | 100 |
| fc2GigEStreamChannel | 183 |
| | 185 |
| Information about a single GigE stream channel | 100 |

Data Structure Index

| fc2H264Option |
|--|
| Options for saving H264 files |
| fc2ImageMetadata |
| Metadata related to an image |
| fc2InternalContext |
| fc2InternalGuiContext |
| fc2InternalImageCallback |
| fc2IPAddress |
| IPv4 address |
| fc2JPEGOption |
| Options for saving JPEG image |
| fc2JPG2Option |
| Options for saving JPEG2000 image |
| fc2LUTData |
| Information about the camera's look up table |
| fc2MACAddress |
| MAC address |
| fc2MJPGOption |
| Options for saving MJPG files |
| fc2PGMOption |
| Options for saving PGM images |
| fc2PGRGuid |
| A GUID to the camera |
| fc2PNGOption Options for saving PNG images |
| fc2PPMOption |
| Options for saving PPM images |
| fc2StrobeControl |
| A camera strobe |
| fc2StrobeInfo |
| A camera strobe property |
| fc2SystemInfo |
| Description of the system |
| fc2TIFFOption fc2TIFFOption |
| Options for saving TIFF images |
| fc2TimeStamp |
| Timestamp information |
| fc2TriggerDelay |
| A specific camera property |
| fc2TriggerDelayInfo |
| Information about a specific camera property |
| fc2TriggerMode |
| A camera trigger |
| fc2TriggerModeInfo |
| Information about a camera trigger property |
| fc2Version |
| The current version of the library |

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

| -lyCapture2_C.h |
|--------------------------------------|
| -TyCapture2Defs_C.h |
| -TyCapture2GUI_C.h |
| -TyCapture2Internal_C.h |
| -TyCapture2Platform_C.h |
| -TyCapture2Private_C.h |
| -TyCapture2Video_C.h |
| -lyCapture2VideoDefs_C.h |
| MultiSyncLibrary_C.h |
| MultiSyncLibraryDefs_C.h 266 |
| AultiSyncLibraryPlatform C.h |

10 File Index

Chapter 6

Module Documentation

6.1 Bus Manager Operation

The functions in this section provide access to BusManager operations.

Functions

- FLYCAPTURE2_C_API fc2Error fc2FireBusReset (fc2Context context, fc2PGRGuid *pGuid)
 Fire a bus reset.
- FLYCAPTURE2_C_API fc2Error fc2GetNumOfCameras (fc2Context context, unsigned int *pNumCameras)

 Gets the number of cameras attached to the PC.
- FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIPAddress (fc2Context context, fc2IPAddress ip
 — Address, fc2PGRGuid *pGuid)

Gets the PGRGuid for a camera with the specified IPv4 address.

FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIndex (fc2Context context, unsigned int index, fc2PG
 — RGuid *pGuid)

Gets the PGRGuid for a camera on the PC.

FLYCAPTURE2_C_API fc2Error fc2GetCameraFromSerialNumber (fc2Context context, unsigned int serial
 — Number, fc2PGRGuid *pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2_C_API fc2Error fc2GetCameraSerialNumberFromIndex (fc2Context context, unsigned int index, unsigned int *pSerialNumber)

Gets the serial number of the camera with the specified index.

FLYCAPTURE2_C_API fc2Error fc2GetInterfaceTypeFromGuid (fc2Context context, fc2PGRGuid *pGuid, fc2InterfaceType *pInterfaceType)

Gets the interface type associated with a PGRGuid.

- FLYCAPTURE2_C_API fc2Error fc2GetNumOfDevices (fc2Context context, unsigned int *pNumDevices)

 Gets the number of devices.
- FLYCAPTURE2_C_API fc2Error fc2GetDeviceFromIndex (fc2Context context, unsigned int index, fc2PGR← Guid *pGuid)

Gets the PGRGuid for a device.

• FLYCAPTURE2_C_API fc2Error fc2ReadPhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int *pValue)

Read a phy register on the specified device.

• FLYCAPTURE2_C_API fc2Error fc2WritePhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)

Write a phy register on the specified device.

 FLYCAPTURE2_C_API fc2Error fc2GetUsbLinkInfo (fc2Context context, fc2PGRGuid guid, unsigned int *pValue)

Read usb link info for the port that the specified device is connected to.

 FLYCAPTURE2_C_API fc2Error fc2GetUsbPortStatus (fc2Context context, fc2PGRGuid guid, unsigned int *pValue)

Read usb port status for the port that the specified device is connected to.

Gets the topology information for the PC.

• FLYCAPTURE2_C_API fc2Error fc2RegisterCallback (fc2Context context, fc2BusEventCallback enum ← Callback, fc2BusCallbackType callbackType, void *pParameter, fc2CallbackHandle *pCallbackHandle)

Register a callback function that will be called when the specified callback event occurs.

 FLYCAPTURE2_C_API fc2Error fc2UnregisterCallback (fc2Context context, fc2CallbackHandle callback← Handle)

Unregister a callback function.

• FLYCAPTURE2 C API fc2Error fc2RescanBus (fc2Context context)

Force a rescan of the buses.

• FLYCAPTURE2_C_API fc2Error fc2ForceIPAddressToCamera (fc2Context context, fc2MACAddress mac← Address, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

• FLYCAPTURE2_C_API fc2Error fc2ForceAllIPAddressesAutomatically ()

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

FLYCAPTURE2_C_API fc2Error fc2ForceIPAddressAutomatically (unsigned int serialNumber)

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

• FLYCAPTURE2_C_API fc2Error fc2DiscoverGigECameras (fc2Context context, fc2CameraInfo *gigE← Cameras, unsigned int *arraySize)

Discover all cameras connected to the network even if they reside on a different subnet.

FLYCAPTURE2_C_API fc2Error fc2IsCameraControlable (fc2Context context, fc2PGRGuid *pGuid, BOOL *pControlable)

Query whether a GigE camera is controllable.

6.1.1 Detailed Description

The functions in this section provide access to BusManager operations.

6.1.2 Function Documentation

6.1.2.1 fc2DiscoverGigECameras()

Discover all cameras connected to the network even if they reside on a different subnet.

This is useful in situations where a GigE camera is using Persistent IP and the application's subnet is different from the device subnet. After discovering the camera, it is easy to use ForceIPAddressToCamera() to set a different IP configuration.

Parameters

| context | The fc2Context to be used. |
|---|---|
| gigECameras | Pointer to an array of CameraInfo structures. |
| arraySize Size of the array. Number of discovered cameras is returned in the same value | |

Returns

An Error indicating the success or failure of the function. If the error is PGRERROR_BUFFER_TOO_SMALL then arraySize will contain the minimum size needed for gigECameras array.

6.1.2.2 fc2FireBusReset()

Fire a bus reset.

The actual bus reset is only fired for the specified 1394 bus, but it will effectively cause a global bus reset for the library.

Parameters

| context | The fc2Context to be used. |
|---------|---|
| pGuid | PGRGuid of the camera or the device to cause bus reset. |

Returns

An Error indicating the success or failure of the function.

6.1.2.3 fc2ForceAllIPAddressesAutomatically()

```
FLYCAPTURE2_C_API fc2Error fc2ForceAllIPAddressesAutomatically ( )
```

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

This is useful in situations where GigE Vision cameras are using IP addresses in a subnet different from the host's subnet.

Returns

An Error indicating the success or failure of the function.

6.1.2.4 fc2ForcelPAddressAutomatically()

```
\label{lem:flycapture2_C_API fc2Error fc2ForceIPAddressAutomatically (} \\ \text{unsigned int } serialNumber \ )
```

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

This is useful in situations where GigE Vision cameras are using IP addresses in a subnet different from the host's subnet.

Returns

An Error indicating the success or failure of the function.

6.1.2.5 fc2ForcelPAddressToCamera()

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

This is useful in situations where a GigE Vision camera is using Persistent IP and the application's subnet is different from the device subnet.

Parameters

| context | The fc2Context to be used. |
|----------------|---------------------------------------|
| macAddress | MAC address of the camera. |
| ipAddress | IP address to set on the camera. |
| subnetMask | Subnet mask to set on the camera. |
| defaultGateway | Default gateway to set on the camera. |

Returns

An Error indicating the success or failure of the function.

6.1.2.6 fc2GetCameraFromIndex()

Gets the PGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the index and is used to identify the camera during a fc2Connect() call.

Parameters

| context | The fc2Context to be used. |
|---------|--------------------------------|
| index | Zero based index of camera. |
| pGuid | Unique PGRGuid for the camera. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.7 fc2GetCameraFromIPAddress()

Gets the PGRGuid for a camera with the specified IPv4 address.

Parameters

| context | The fc2Context to be used. |
|-----------|--------------------------------|
| ipAddress | IP address to get GUID for. |
| pGuid | Unique PGRGuid for the camera. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.8 fc2GetCameraFromSerialNumber()

Gets the PGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the serial number and is used to identify the camera during a fc2 Connect() call.

| context | The fc2Context to be used. |
|--------------|--------------------------------|
| serialNumber | Serial number of camera. |
| pGuid | Unique PGRGuid for the camera. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.9 fc2GetCameraSerialNumberFromIndex()

Gets the serial number of the camera with the specified index.

Parameters

| context | The fc2Context to be used. |
|---------------|-------------------------------------|
| index | Zero based index of desired camera. |
| pSerialNumber | Serial number of camera. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.10 fc2GetDeviceFromIndex()

Gets the PGRGuid for a device.

It uniquely identifies the device specified by the index.

Parameters

| context | The fc2Context to be used. |
|---------|--------------------------------|
| index | Zero based index of device. |
| pGuid | Unique PGRGuid for the device. |

See also

fc2GetNumOfDevices()

Returns

An Error indicating the success or failure of the function.

6.1.2.11 fc2GetInterfaceTypeFromGuid()

Gets the interface type associated with a PGRGuid.

This is useful in situations where there is a need to enumerate all cameras for a particular interface.

Parameters

| context | The fc2Context to be used. |
|----------------|---------------------------------------|
| pGuid | The PGRGuid to get the interface for. |
| pInterfaceType | The interface type of the PGRGuid. |

Returns

6.1.2.12 fc2GetNumOfCameras()

Gets the number of cameras attached to the PC.

Parameters

| context | The fc2Context to be used. |
|-------------|-----------------------------|
| pNumCameras | Number of cameras detected. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.13 fc2GetNumOfDevices()

Gets the number of devices.

This may include hubs, host controllers and other hardware devices (including cameras).

Parameters

| context | The fc2Context to be used. |
|-------------|------------------------------|
| pNumDevices | The number of devices found. |

Returns

An Error indicating the success or failure of the function.

6.1.2.14 fc2GetTopology()

Gets the topology information for the PC.

Parameters

| context | The fc2Context to be used. |
|----------------------|--|
| pTopologyNodeContext | A Topology Node context that will contain the topology information |

Returns

An Error indicating the success or failure of the function.

6.1.2.15 fc2GetUsbLinkInfo()

Read usb link info for the port that the specified device is connected to.

Parameters

| context | The fc2Context to be used. |
|---------|------------------------------------|
| guid | Unique PGRGuid for the device. |
| pValue | Value read from the card register. |

Returns

An Error indicating the success or failure of the function.

6.1.2.16 fc2GetUsbPortStatus()

Read usb port status for the port that the specified device is connected to.

Parameters

| context | The fc2Context to be used. |
|---------|------------------------------------|
| guid | Unique PGRGuid for the device. |
| pValue | Value read from the card register. |

Returns

An Error indicating the success or failure of the function.

6.1.2.17 fc2lsCameraControlable()

Query whether a GigE camera is controllable.

| context | The fc2Context to be used. |
|---------------|---------------------------------------|
| pGuid | Unique PGRGuid for the camera. |
| pControllable | True indicates camera is controllable |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.18 fc2ReadPhyRegister()

```
FLYCAPTURE2_C_API fc2Error fc2ReadPhyRegister (
    fc2Context context,
    fc2PGRGuid guid,
    unsigned int page,
    unsigned int port,
    unsigned int address,
    unsigned int * pValue )
```

Read a phy register on the specified device.

The full address to be read from is determined by the page, port and address.

Parameters

| context | The fc2Context to be used. |
|---------|-----------------------------------|
| guid | Unique PGRGuid for the device. |
| page | Page to read from. |
| port | Port to read from. |
| address | Address to read from. |
| pValue | Value read from the phy register. |

Returns

An Error indicating the success or failure of the function.

6.1.2.19 fc2RegisterCallback()

Register a callback function that will be called when the specified callback event occurs.

| context | The fc2Context to be used. |
|-----------------------|---|
| enumCallback | Pointer to function that will receive the callback. |
| callbackType | Type of callback to register for. |
| pParameter | Callback parameter to be passed to callback. |
| с ысырысынал ы | Unique callback handle used for unregistering callback. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.20 fc2RescanBus()

Force a rescan of the buses.

This does not trigger a bus reset. The camera objects will be invalidated only if the camera network topology is changed (ie. a camera is disconnected or added)

Returns

An Error indicating the success or failure of the function.

6.1.2.21 fc2UnregisterCallback()

Unregister a callback function.

Parameters

| context | The fc2Context to be used. |
|----------------|----------------------------|
| callbackHandle | Unique callback handle. |

Returns

A fc2Error indicating the success or failure of the function.

6.1.2.22 fc2WritePhyRegister()

```
unsigned int address,
unsigned int value )
```

Write a phy register on the specified device.

The full address to be written to is determined by the page, port and address.

Parameters

| context | The fc2Context to be used. |
|---------|---------------------------------|
| guid | Unique PGRGuid for the device. |
| page | Page to write to. |
| port | Port to write to. |
| address | Address to write to. |
| value | Value to write to phy register. |

Returns

An Error indicating the success or failure of the function.

6.2 Connection and Image Retrieval

These functions deal with connections and image retrieval from the camera.

Functions

• FLYCAPTURE2 C API fc2Error fc2Connect (fc2Context context, fc2PGRGuid *guid)

Connects the fc2Context to the camera specified by the GUID.

FLYCAPTURE2_C_API fc2Error fc2Disconnect (fc2Context context)

Disconnects the fc2Context from the camera.

• FLYCAPTURE2 C API BOOL fc2lsConnected (fc2Context context)

Checks if the fc2Context is connected to a physical camera specified by a GUID.

FLYCAPTURE2_C_API fc2Error fc2SetCallback (fc2Context context, fc2ImageEventCallback pCallbackFn, void *pCallbackData)

Sets the callback data to be used on completion of image transfer.

• FLYCAPTURE2 C API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

FLYCAPTURE2_C_API fc2Error fc2StartCaptureCallback (fc2Context context, fc2ImageEventCallback p
 — CallbackFn, void *pCallbackData)

Starts isochronous image capture.

• FLYCAPTURE2_C_API fc2Error fc2StartSyncCapture (unsigned int numCameras, fc2Context *pContexts)

Starts synchronized isochronous image capture on multiple cameras.

FLYCAPTURE2_C_API fc2Error fc2StartSyncCaptureCallback (unsigned int numCameras, fc2Context *p←
 Contexts, fc2ImageEventCallback *pCallbackFns, void **pCallbackDataArray)

Starts synchronized isochronous image capture on multiple cameras.

FLYCAPTURE2_C_API fc2Error fc2RetrieveBuffer (fc2Context context, fc2Image *pImage)

Retrieves the next image object containing the next image.

• FLYCAPTURE2 C API fc2Error fc2StopCapture (fc2Context context)

Stops isochronous image transfer and cleans up all associated resources.

FLYCAPTURE2_C_API fc2Error fc2WaitForBufferEvent (fc2Context context, fc2Image *pImage, unsigned int eventNumber)

Retrieves the next image event containing the next part of the image.

FLYCAPTURE2_C_API fc2Error fc2SetUserBuffers (fc2Context context, unsigned char *const ppMem
 — Buffers, int size, int nNumBuffers)

Specify user allocated buffers to use as image data buffers.

• FLYCAPTURE2_C_API fc2Error fc2GetConfiguration (fc2Context context, fc2Config *config)

Get the configuration associated with the camera.

FLYCAPTURE2_C_API fc2Error fc2SetConfiguration (fc2Context context, fc2Config *config)

Set the configuration associated with the camera.

6.2.1 Detailed Description

These functions deal with connections and image retrieval from the camera.

6.2.2 Function Documentation

6.2.2.1 fc2Connect()

Connects the fc2Context to the camera specified by the GUID.

Be aware that calling fc2CreateGUIContext() releases the CCP acquired for GigE cameras in fc2Connect(). Consider calling fc2Connect() after fc2CreateGUIContext().

Parameters

| context | The fc2Context to be used. |
|---------|--|
| guid | The unique identifier for a specific camera on the PC. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.2 fc2Disconnect()

Disconnects the fc2Context from the camera.

This allows another physical camera specified by a GUID to be connected to the fc2Context.

See also

fc2Connect()

Parameters

| context The fc2Context to be used. |
|------------------------------------|
|------------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.3 fc2GetConfiguration()

Get the configuration associated with the camera.

See also

fc2SetConfiguration()

Parameters

| context | The fc2Context to be used. |
|---------|--|
| config | Pointer to the configuration structure to be filled. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.4 fc2lsConnected()

Checks if the fc2Context is connected to a physical camera specified by a GUID.

See also

```
fc2Connect()
fc2Disconnect()
```

Parameters

| context | The fc2Context to be used. |
|---------|----------------------------|

Returns

Whether fc2Connect() was called on the fc2Context.

6.2.2.5 fc2RetrieveBuffer()

Retrieves the next image object containing the next image.

See also

```
fc2StartCapture()
fc2StopCapture()
```

Parameters

| context | The fc2Context to be used. |
|---------|--|
| plmage | Pointer to fc2Image to store image data. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.6 fc2SetCallback()

Sets the callback data to be used on completion of image transfer.

To clear the current stored callback data, pass in NULL for both callback arguments.

See also

fc2StartCapture()

Parameters

| context | The fc2Context to be used. |
|---------------|--|
| pCallbackFn | A function to be called when a new image is received. |
| pCallbackData | A pointer to data that can be passed to the callback function. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.7 fc2SetConfiguration()

Set the configuration associated with the camera.

See also

fc2GetConfiguration()

Parameters

| context | The fc2Context to be used. |
|---------|--|
| config | Pointer to the configuration structure to be used. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.8 fc2SetUserBuffers()

Specify user allocated buffers to use as image data buffers.

To prevent image tearing, the size of each buffer should be equal to ((unsigned int)(bufferSize + packetSize - 1)/packetSize) * packetSize. The total size should be (size * numBuffers) or larger. The packet Size that should be used differs between interfaces: Firewire: Use the Format7 packet size. Usb2: First round to Format7 packet size then round to 512 bytes. Usb3: Use a packet size of 1024 bytes. GigE: No need to do any rounding on GigE

See also

fc2StartCapture() fc2RetrieveBuffer() fc2StopCapture()

Parameters

| context | The fc2Context to be used. |
|--------------|---|
| ppMemBuffers | Pointer to memory buffers to be written to. The size of the data should be equal to (size \ast numBuffers) or larger. |
| size | The size of each buffer (in bytes). |
| nNumBuffers | Number of buffers in the array. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.9 fc2StartCapture()

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera.

See also

```
fc2RetrieveBuffer()
fc2StartSyncCapture()
fc2StopCapture()
```

Parameters

| | context | The fc2Context to be used. |
|--|---------|----------------------------|
|--|---------|----------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.10 fc2StartCaptureCallback()

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera. The callback function is called when a new image is received from the camera.

See also

```
fc2RetrieveBuffer()
fc2StartSyncCapture()
fc2StopCapture()
```

Parameters

| context | The fc2Context to be used. |
|---------------|--|
| pCallbackFn | A function to be called when a new image is received. |
| pCallbackData | A pointer to data that can be passed to the callback function. A NULL pointer is acceptable. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.11 fc2StartSyncCapture()

Starts synchronized isochronous image capture on multiple cameras.

This function is only used for firewire cameras.

See also

```
fc2RetrieveBuffer()
fc2StartCapture()
fc2StopCapture()
```

Parameters

| numCameras | Number of fc2Contexts in the ppCameras array. |
|------------|---|
| pContexts | Array of fc2Contexts. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.12 fc2StartSyncCaptureCallback()

```
FLYCAPTURE2_C_API fc2Error fc2StartSyncCaptureCallback (
    unsigned int numCameras,
    fc2Context * pContexts,
    fc2ImageEventCallback * pCallbackFns,
    void ** pCallbackDataArray )
```

Starts synchronized isochronous image capture on multiple cameras.

This function is only used for firewire cameras.

See also

```
fc2RetrieveBuffer()
fc2StartCapture()
fc2StopCapture()
```

| numCameras | Number of fc2Contexts in the ppCameras array. |
|--------------------|---|
| pContexts | Array of fc2Contexts. |
| pCallbackFns | Array of callback functions for each camera. |
| pCallbackDataArray | Array of callback data pointers. |

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.13 fc2StopCapture()

Stops isochronous image transfer and cleans up all associated resources.

See also

```
fc2StartCapture()
fc2RetrieveBuffer()
```

Parameters

| (| context | The fc2Context to be used. |
|---|---------|----------------------------|
|---|---------|----------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.2.2.14 fc2WaitForBufferEvent()

Retrieves the next image event containing the next part of the image.

See also

```
fc2StartCapture()
fc2RetrieveBuffer()
fc2StopCapture()
```

| context | The fc2Context to be used. |
|-------------|--|
| plmage | Pointer to fc2Image to store image data. |
| eventNumber | The event number to wait for. |

An Error indicating the success or failure of the function.

6.3 Information and Properties

These functions deal with information and properties can be retrieved from the camera.

Functions

- FLYCAPTURE2_C_API fc2Error fc2GetCameraInfo (fc2Context context, fc2CameraInfo *pCameraInfo)

 Retrieves information from the camera such as serial number, model name and other camera information.
- FLYCAPTURE2_C_API fc2Error fc2GetPropertyInfo (fc2Context context, fc2PropertyInfo *propInfo)

 Retrieves information about the specified camera property.
- FLYCAPTURE2_C_API fc2Error fc2GetProperty (fc2Context context, fc2Property *prop)

 Reads the settings for the specified property from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetProperty (fc2Context context, fc2Property *prop) Writes the settings for the specified property to the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetPropertyBroadcast (fc2Context context, fc2Property *prop)

 Writes the settings for the specified property to the camera.

6.3.1 Detailed Description

These functions deal with information and properties can be retrieved from the camera.

6.3.2 Function Documentation

6.3.2.1 fc2GetCameraInfo()

Retrieves information from the camera such as serial number, model name and other camera information.

Parameters

| context | The fc2Context to be used. |
|-------------|---|
| pCameraInfo | Pointer to the camera information structure to be filled. |

Returns

A fc2Error indicating the success or failure of the function.

6.3.2.2 fc2GetProperty()

Reads the settings for the specified property from the camera.

The property type must be specified in the fc2Property structure passed into the function in order for the function to succeed. If auto is on, the integer and abs values returned may not be consistent with each other.

See also

```
fc2GetPropertyInfo()
fc2SetProperty()
```

Parameters

| context | The fc2Context to be used. |
|---------|---|
| prop | Pointer to the Property structure to be filled. |

Returns

A fc2Error indicating the success or failure of the function.

6.3.2.3 fc2GetPropertyInfo()

Retrieves information about the specified camera property.

The property type must be specified in the fc2PropertyInfo structure passed into the function in order for the function to succeed.

See also

```
fc2GetProperty()
fc2SetProperty()
```

| context | The fc2Context to be used. |
|----------|---|
| propInfo | Pointer to the PropertyInfo structure to be filled. |

Returns

A fc2Error indicating the success or failure of the function.

6.3.2.4 fc2SetProperty()

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera. Use fc2GetPropertyInfo() to query which options are available for a specific property.

See also

```
fc2GetPropertyInfo()
fc2GetProperty()
```

Parameters

| context | The fc2Context to be used. |
|---------|---|
| prop | Pointer to the Property structure to be used. |

Returns

A fc2Error indicating the success or failure of the function.

6.3.2.5 fc2SetPropertyBroadcast()

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera.

| context | The fc2Context to be used. |
|---------|---|
| prop | Pointer to the Property structure to be used. |

A fc2Error indicating the success or failure of the function.

6.4 General Purpose Input / Output

These functions deal with general GPIO pin control on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int *pDirection)

Get the GPIO pin direction for the specified pin.

• FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirectionBroadcast (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

6.4.1 Detailed Description

These functions deal with general GPIO pin control on the camera.

6.4.2 Function Documentation

6.4.2.1 fc2GetGPIOPinDirection()

Get the GPIO pin direction for the specified pin.

This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

See also

```
fc2SetGPIOPinDirection()
fc2SetGPIOPinDirectionBroadcast()
```

| context | The fc2Context to be used. |
|------------|--|
| pin | Pin to get the direction for. |
| pDirection | Direction of the pin. 0 for input, 1 for output. |

Returns

A fc2Error indicating the success or failure of the function.

6.4.2.2 fc2SetGPIOPinDirection()

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

See also

```
fc2GetGPIOPinDirection()
fc2SetGPIOPinDirectionBroadcast()
```

Parameters

| context | The fc2Context to be used. |
|-----------|--|
| pin | Pin to get the direction for. |
| direction | Direction of the pin. 0 for input, 1 for output. |

Returns

A fc2Error indicating the success or failure of the function.

6.4.2.3 fc2SetGPIOPinDirectionBroadcast()

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

See also

fc2GetGPIOPinDirection()

Parameters

| context | The fc2Context to be used. |
|-----------|--|
| pin | Pin to get the direction for. |
| direction | Direction of the pin. 0 for input, 1 for output. |

Returns

A fc2Error indicating the success or failure of the function.

6.5 Trigger 41

6.5 Trigger

These functions deal with trigger control on the camera.

Functions

Retrieve trigger information from the camera.

- FLYCAPTURE2_C_API fc2Error fc2GetTriggerMode (fc2Context context, fc2TriggerMode *triggerMode)

 Retrieve current trigger settings from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerMode (fc2Context context, fc2TriggerMode *triggerMode)

 Set the specified trigger settings to the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerModeBroadcast (fc2Context context, fc2TriggerMode *triggerMode)

Set the specified trigger settings to the camera.

FLYCAPTURE2_C_API fc2Error fc2FireSoftwareTrigger (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2_C_API fc2Error fc2FireSoftwareTriggerBroadcast (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelayInfo (fc2Context context, fc2TriggerDelayInfo *trigger
 — DelayInfo)

Retrieve trigger delay information from the camera.

- FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelay (fc2Context context, fc2TriggerDelay *triggerDelay)

 *Retrieve current trigger delay settings from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelay (fc2Context context, fc2TriggerDelay *triggerDelay) Set the specified trigger delay settings to the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelayBroadcast (fc2Context context, fc2TriggerDelay *triggerDelay)

Set the specified trigger delay settings to the camera.

6.5.1 Detailed Description

These functions deal with trigger control on the camera.

6.5.2 Function Documentation

6.5.2.1 fc2FireSoftwareTrigger()

Fire the software trigger according to the DCAM specifications.

Parameters

| context The fc2Context to be used. |
|--------------------------------------|
|--------------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.2 fc2FireSoftwareTriggerBroadcast()

Fire the software trigger according to the DCAM specifications.

Parameters

| context The fc2Context to be used. |
|------------------------------------|
|------------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.3 fc2GetTriggerDelay()

Retrieve current trigger delay settings from the camera.

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2SetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

| context | The fc2Context to be used. |
|--------------|--|
| triggerDelay | Structure to receive trigger delay settings. |

6.5 Trigger 43

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.4 fc2GetTriggerDelayInfo()

Retrieve trigger delay information from the camera.

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

Parameters

| context | The fc2Context to be used. |
|------------------|---|
| triggerDelayInfo | Structure to receive trigger delay information. |

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.5 fc2GetTriggerMode()

Retrieve current trigger settings from the camera.

See also

```
fc2GetTriggerModeInfo()
fc2SetTriggerMode()
fc2SetTriggerModeBroadcast()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
```

Parameters

| context | The fc2Context to be used. |
|-------------|---|
| triggerMode | Structure to receive trigger mode settings. |

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.6 fc2GetTriggerModeInfo()

Retrieve trigger information from the camera.

See also

```
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2SetTriggerModeBroadcast()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
```

Parameters

| context | The fc2Context to be used. |
|-----------------|---|
| triggerModeInfo | Structure to receive trigger information. |

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.7 fc2SetTriggerDelay()

Set the specified trigger delay settings to the camera.

6.5 Trigger 45

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

Parameters

| context | The fc2Context to be used. |
|--------------|---|
| triggerDelay | Structure providing trigger delay settings. |

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.8 fc2SetTriggerDelayBroadcast()

Set the specified trigger delay settings to the camera.

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
```

Parameters

| context | The fc2Context to be used. |
|--------------|---|
| triggerDelay | Structure providing trigger delay settings. |

Returns

6.5.2.9 fc2SetTriggerMode()

Set the specified trigger settings to the camera.

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
fc2SetTriggerModeBroadcast()
```

Parameters

| context | The fc2Context to be used. |
|-------------|--|
| triggerMode | Structure providing trigger mode settings. |

Returns

A fc2Error indicating the success or failure of the function.

6.5.2.10 fc2SetTriggerModeBroadcast()

Set the specified trigger settings to the camera.

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2GetTriggerDelayInfo()
fc2GetTriggerDelay()
fc2SetTriggerDelay()
fc2SetTriggerMode()
```

| context | The fc2Context to be used. |
|-------------|--|
| triggerMode | Structure providing trigger mode settings. |

6.5 Trigger 47

6.6 Strobe

These functions deal with strobe control on the camera.

Functions

- FLYCAPTURE2_C_API fc2Error fc2GetStrobeInfo (fc2Context context, fc2StrobeInfo *strobeInfo)

 Retrieve strobe information from the camera.
- FLYCAPTURE2_C_API fc2Error fc2GetStrobe (fc2Context context, fc2StrobeControl *strobeControl)

 Retrieve current strobe settings from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetStrobe (fc2Context context, fc2StrobeControl *strobeControl) Set current strobe settings to the camera.

Set current strobe settings to the camera.

6.6.1 Detailed Description

These functions deal with strobe control on the camera.

6.6.2 Function Documentation

6.6.2.1 fc2GetStrobe()

Retrieve current strobe settings from the camera.

The strobe pin must be specified in the structure before being passed in to the function.

See also

```
fc2GetStrobeInfo()
fc2SetStrobe()
fc2SetStrobeBroadcast()
```

| context | The fc2Context to be used. |
|---------------|---------------------------------------|
| strobeControl | Structure to receive strobe settings. |

6.6 Strobe 49

Returns

A fc2Error indicating the success or failure of the function.

6.6.2.2 fc2GetStrobeInfo()

Retrieve strobe information from the camera.

See also

```
fc2GetStrobe()
fc2SetStrobeBroadcast()
```

Parameters

| context | The fc2Context to be used. |
|------------|--|
| strobeInfo | Structure to receive strobe information. |

Returns

A fc2Error indicating the success or failure of the function.

6.6.2.3 fc2SetStrobe()

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

See also

```
fc2GetStrobeInfo()
fc2GetStrobe()
fc2SetStrobeBroadcast()
```

| context | The fc2Context to be used. |
|---------------|--------------------------------------|
| strobeControl | Structure providing strobe settings. |

Returns

A fc2Error indicating the success or failure of the function.

6.6.2.4 fc2SetStrobeBroadcast()

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

See also

```
fc2GetStrobeInfo()
fc2GetStrobe()
fc2SetStrobe()
```

Parameters

| ĺ | context | The fc2Context to be used. | Ì |
|---|---------------|--------------------------------------|---|
| | strobeControl | Structure providing strobe settings. | |

Returns

6.7 Look Up Table 51

6.7 Look Up Table

These functions deal with Look Up Table control on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetLUTInfo (fc2Context context, fc2LUTData *pData)

Query if LUT support is available on the camera.

 FLYCAPTURE2_C_API fc2Error fc2GetLUTBankInfo (fc2Context context, unsigned int bank, BOOL *p↔ ReadSupported, BOOL *pWriteSupported)

Query the read/write status of a single LUT bank.

- FLYCAPTURE2_C_API fc2Error fc2GetActiveLUTBank (fc2Context context, unsigned int *pActiveBank)
 - Get the LUT bank that is currently being used.
- FLYCAPTURE2_C_API fc2Error fc2SetActiveLUTBank (fc2Context context, unsigned int activeBank)

Set the LUT bank that will be used.

• FLYCAPTURE2_C_API fc2Error fc2EnableLUT (fc2Context context, BOOL on)

Enable or disable LUT functionality on the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)

Get the LUT channel settings from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)

Set the LUT channel settings to the camera.

6.7.1 Detailed Description

These functions deal with Look Up Table control on the camera.

6.7.2 Function Documentation

6.7.2.1 fc2EnableLUT()

Enable or disable LUT functionality on the camera.

See also

```
fc2GetLUTInfo()
fc2GetLUTChannel()
fc2SetLUTChannel()
```

Parameters

| context | The fc2Context to be used. |
|---------|-----------------------------------|
| on | Whether to enable or disable LUT. |

Returns

A fc2Error indicating the success or failure of the function.

6.7.2.2 fc2GetActiveLUTBank()

Get the LUT bank that is currently being used.

For cameras with PGR LUT, the active bank is always 0.

Parameters

| context | The fc2Context to be used. |
|-------------|----------------------------|
| pActiveBank | The currently active bank. |

Returns

A fc2Error indicating the success or failure of the function.

6.7.2.3 fc2GetLUTBankInfo()

Query the read/write status of a single LUT bank.

| context | The fc2Context to be used. |
|-----------------|---|
| bank | The bank to query. |
| pReadSupported | Whether reading from the bank is supported. |
| pWriteSupported | Whether writing to the bank is supported. |

6.7 Look Up Table 53

Returns

A fc2Error indicating the success or failure of the function.

6.7.2.4 fc2GetLUTChannel()

Get the LUT channel settings from the camera.

See also

```
fc2GetLUTInfo()
fc2EnableLUT()
fc2SetLUTChannel()
```

Parameters

| context | The fc2Context to be used. |
|-------------|---|
| bank | Bank to retrieve. |
| channel | Channel to retrieve. |
| sizeEntries | Number of entries in LUT table to read. |
| pEntries | Array to store LUT entries. |

Returns

A fc2Error indicating the success or failure of the function.

6.7.2.5 fc2GetLUTInfo()

Query if LUT support is available on the camera.

Note that some cameras may report support for the LUT and return an inputBitDepth of 0. In these cases use log2(numEntries) for the inputBitDepth.

See also

```
fc2EnableLUT()
fc2GetLUTChannel()
fc2SetLUTChannel()
```

Parameters

| context | The fc2Context to be used. |
|---------|---------------------------------|
| pData | The LUT structure to be filled. |

Returns

A fc2Error indicating the success or failure of the function.

6.7.2.6 fc2SetActiveLUTBank()

Set the LUT bank that will be used.

Parameters

| context | The fc2Context to be used. |
|------------|-------------------------------|
| activeBank | The bank to be set as active. |

Returns

A fc2Error indicating the success or failure of the function.

6.7.2.7 fc2SetLUTChannel()

```
FLYCAPTURE2_C_API fc2Error fc2SetLUTChannel (
    fc2Context context,
    unsigned int bank,
    unsigned int channel,
    unsigned int sizeEntries,
    unsigned int * pEntries )
```

Set the LUT channel settings to the camera.

See also

fc2GetLUTInfo()
fc2EnableLUT()
fc2GetLUTChannel()

6.7 Look Up Table 55

Parameters

| context | The fc2Context to be used. |
|-------------|---|
| bank | Bank to set. |
| channel | Channel to set. |
| sizeEntries | Number of entries in LUT table to write. This must be the same size as numEntries returned by GetLutInfo(). |
| pEntries | Array containing LUT entries to write. |

Returns

6.8 Memory Channels

These functions deal with memory channel control on the camera.

Functions

FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannel (fc2Context context, unsigned int *pCurrent
 — Channel)

Retrieve the current memory channel from the camera.

- FLYCAPTURE2_C_API fc2Error fc2SaveToMemoryChannel (fc2Context context, unsigned int channel) Save the current settings to the specified current memory channel.
- FLYCAPTURE2_C_API fc2Error fc2RestoreFromMemoryChannel (fc2Context context, unsigned int channel)

 Restore the specified current memory channel.
- FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannelInfo (fc2Context context, unsigned int *pNum← Channels)

Query the camera for memory channel support.

FLYCAPTURE2_C_API fc2Error fc2GetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo *pInfo)

Get the current status of the embedded image information register, as well as the availability of each embedded property.

FLYCAPTURE2_C_API fc2Error fc2SetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo *pInfo)

Sets the on/off values of the embedded image information structure to the camera.

6.8.1 Detailed Description

These functions deal with memory channel control on the camera.

6.8.2 Function Documentation

6.8.2.1 fc2GetEmbeddedImageInfo()

Get the current status of the embedded image information register, as well as the availability of each embedded property.

See also

fc2SetEmbeddedImageInfo()

6.8 Memory Channels 57

Parameters

| context | The fc2Context to be used. |
|---------|----------------------------|
| pInfo | Structure to be filled. |

Returns

A fc2Error indicating the success or failure of the function.

6.8.2.2 fc2GetMemoryChannel()

Retrieve the current memory channel from the camera.

See also

```
fc2SaveToMemoryChannel()
fc2RestoreFromMemoryChannel()
fc2GetMemoryChannelInfo()
```

Parameters

| context | The fc2Context to be used. |
|-----------------|----------------------------|
| pCurrentChannel | Current memory channel. |

Returns

A fc2Error indicating the success or failure of the function.

6.8.2.3 fc2GetMemoryChannelInfo()

```
\label{eq:flycapture2_c_api fc2Error} FLYCAPTURE2\_c\_API fc2Error fc2GetMemoryChannelInfo ( \\ fc2Context context, \\ unsigned int * pNumChannels )
```

Query the camera for memory channel support.

If the number of channels are 0, then memory channel support is not available.

See also

```
fc2GetMemoryChannel()
fc2SaveToMemoryChannel()
fc2RestoreFromMemoryChannel()
```

Parameters

| context | The fc2Context to be used. |
|--------------|--------------------------------------|
| pNumChannels | Number of memory channels supported. |

Returns

A fc2Error indicating the success or failure of the function.

6.8.2.4 fc2RestoreFromMemoryChannel()

Restore the specified current memory channel.

See also

```
fc2GetMemoryChannel()
fc2SaveToMemoryChannel()
fc2GetMemoryChannelInfo()
```

Parameters

| context | The fc2Context to be used. |
|---------|---------------------------------|
| channel | Memory channel to restore from. |

Returns

A fc2Error indicating the success or failure of the function.

6.8.2.5 fc2SaveToMemoryChannel()

Save the current settings to the specified current memory channel.

See also

```
fc2GetMemoryChannel()
fc2RestoreFromMemoryChannel()
fc2GetMemoryChannelInfo()
```

6.8 Memory Channels 59

Parameters

| context | The fc2Context to be used. |
|---------|----------------------------|
| channel | Memory channel to save to. |

Returns

A fc2Error indicating the success or failure of the function.

6.8.2.6 fc2SetEmbeddedImageInfo()

Sets the on/off values of the embedded image information structure to the camera.

See also

fc 2 Get Embedded Image In fo ()

Parameters

| context | The fc2Context to be used. |
|---------|----------------------------|
| pInfo | Structure to be used. |

Returns

6.9 Register Operation

These functions deal with register operation on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2WriteRegister (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera.

 FLYCAPTURE2_C_API fc2Error fc2ReadRegister (fc2Context context, unsigned int address, unsigned int *pValue)

Read the specified register from the camera.

• FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera with broadcast.

• FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int *pBuffer, unsigned int length)

Write to the specified register block on the camera.

 FLYCAPTURE2_C_API fc2Error fc2ReadRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int *pBuffer, unsigned int length)

Write to the specified register block on the camera.

• FLYCAPTURE2_C_API const char * fc2GetRegisterString (unsigned int registerVal)

Returns a text representation of the register value.

6.9.1 Detailed Description

These functions deal with register operation on the camera.

6.9.2 Function Documentation

6.9.2.1 fc2GetRegisterString()

Returns a text representation of the register value.

Parameters

| registerVal | The register value to query. |
|-------------|------------------------------|
| | |

Returns

6.9 Register Operation 61

6.9.2.2 fc2ReadRegister()

Read the specified register from the camera.

See also

fc2WriteRegister()

Parameters

| context | The fc2Context to be used. |
|---------|-------------------------------|
| address | DCAM address to be read from. |
| pValue | The value that is read. |

Returns

A fc2Error indicating the success or failure of the function.

6.9.2.3 fc2ReadRegisterBlock()

Write to the specified register block on the camera.

See also

fc2WriteRegisterBlock()

| context | The fc2Context to be used. |
|-------------|--|
| addressHigh | Top 16 bits of the 48-bit absolute address to read from. |
| addressLow | Bottom 32 bits of the 48 bits absolute address to read from. |
| pBuffer | Array to store read data. |
| length | Size of array, in quadlets. |

Returns

A fc2Error indicating the success or failure of the function.

6.9.2.4 fc2WriteRegister()

Write to the specified register on the camera.

See also

fc2ReadRegister()

Parameters

| context | The fc2Context to be used. |
|---------|--------------------------------|
| address | DCAM address to be written to. |
| value | The value to be written. |

Returns

A fc2Error indicating the success or failure of the function.

6.9.2.5 fc2WriteRegisterBlock()

Write to the specified register block on the camera.

See also

fc2ReadRegisterBlock()

Parameters

| context | The fc2Context to be used. |
|-------------|---|
| addressHigh | Top 16 bits of the 48-bit absolute address to write to. |
| addressLow | Bottom 32 bits of the 48 bits absolute address to write to. |
| pBuffer | Array containing data to be written. |
| length | Size of array, in quadlets. |

Generated by Doxygen

Returns

A fc2Error indicating the success or failure of the function.

6.9.2.6 fc2WriteRegisterBroadcast()

Write to the specified register on the camera with broadcast.

See also

fc2ReadRegisterBlock()

Parameters

| context | The fc2Context to be used. |
|---------|--------------------------------|
| address | DCAM address to be written to. |
| value | The value to be written. |

Returns

6.10 DCAM Formats

These functions deal with DCAM video mode and frame rate on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRateInfo (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL *pSupported)

Query the camera to determine if the specified video mode and frame rate is supported.

 FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRate (fc2Context context, fc2VideoMode *videoMode, fc2FrameRate *frameRate)

Get the current video mode and frame rate from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetVideoModeAndFrameRate (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

6.10.1 Detailed Description

These functions deal with DCAM video mode and frame rate on the camera.

This is only used for firewire and usb2 cameras.

6.10.2 Function Documentation

6.10.2.1 fc2GetVideoModeAndFrameRate()

Get the current video mode and frame rate from the camera.

If the camera is in Format7, the video mode will be VIDEOMODE_FORMAT7 and the frame rate will be FRAME← RATE_FORMAT7.

Parameters

| context | The fc2Context to be used. |
|-----------|----------------------------|
| videoMode | Current video mode. |
| frameRate | Current frame rate. |

Returns

6.10 DCAM Formats 65

6.10.2.2 fc2GetVideoModeAndFrameRateInfo()

Query the camera to determine if the specified video mode and frame rate is supported.

Parameters

| context | The fc2Context to be used. | |
|--------------------------------|---|--|
| videoMode | Video mode to check. | |
| frameRate Frame rate to check. | | |
| pSupported | Whether the video mode and frame rate is supported. | |

Returns

A fc2Error indicating the success or failure of the function.

6.10.2.3 fc2SetVideoModeAndFrameRate()

Set the specified video mode and frame rate to the camera.

It is not possible to set the camera to VIDEOMODE_FORMAT7 or FRAMERATE_FORMAT7. Use the Format7 functions to set the camera into Format7.

Parameters

| context | The fc2Context to be used. |
|-----------|------------------------------|
| videoMode | Video mode to set to camera. |
| frameRate | Frame rate to set to camera. |

Returns

6.11 Format7

These functions deal with Format7 custom image control on the camera.

Functions

 FLYCAPTURE2_C_API fc2Error fc2GetFormat7Info (fc2Context context, fc2Format7Info *info, BOOL *p↔ Supported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

 FLYCAPTURE2_C_API fc2Error fc2ValidateFormat7Settings (fc2Context context, fc2Format7ImageSettings *imageSettings, BOOL *settingsAreValid, fc2Format7PacketInfo)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

FLYCAPTURE2_C_API fc2Error fc2GetFormat7Configuration (fc2Context context, fc2Format7Image
 — Settings *imageSettings, unsigned int *packetSize, float *percentage)

Get the current Format7 configuration from the camera.

FLYCAPTURE2_C_API fc2Error fc2SetFormat7ConfigurationPacket (fc2Context context, fc2Format7← ImageSettings *imageSettings, unsigned int packetSize)

Set the current Format7 configuration to the camera.

 FLYCAPTURE2_C_API fc2Error fc2SetFormat7Configuration (fc2Context context, fc2Format7ImageSettings *imageSettings, float percentSpeed)

Set the current Format7 configuration to the camera.

6.11.1 Detailed Description

These functions deal with Format7 custom image control on the camera.

6.11.2 Function Documentation

6.11.2.1 fc2GetFormat7Configuration()

Get the current Format7 configuration from the camera.

This call will only succeed if the camera is already in Format7.

| context | The fc2Context to be used. |
|---------------|--------------------------------------|
| imageSettings | Current image settings. |
| packetSize | Current packet size. |
| percentage | Current packet size as a percentage. |

6.11 Format7 67

Returns

A fc2Error indicating the success or failure of the function.

6.11.2.2 fc2GetFormat7Info()

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

The mode must be specified in the Format7Info structure in order for the function to succeed.

Parameters

| context | The fc2Context to be used. |
|------------|---|
| info | Structure to be filled with the capabilities of the specified mode and the current state in the specified mode. |
| pSupported | Whether the specified mode is supported. |

Returns

A fc2Error indicating the success or failure of the function.

6.11.2.3 fc2SetFormat7Configuration()

Set the current Format7 configuration to the camera.

Parameters

| context | The fc2Context to be used. |
|---------------|--|
| imageSettings | Image settings to be written to the camera. |
| percentSpeed | Packet size as a percentage to be written to the camera. |

Returns

6.11.2.4 fc2SetFormat7ConfigurationPacket()

Set the current Format7 configuration to the camera.

Parameters

| context | The fc2Context to be used. |
|---------------|---|
| imageSettings | Image settings to be written to the camera. |
| packetSize | Packet size to be written to the camera. |

Returns

A fc2Error indicating the success or failure of the function.

6.11.2.5 fc2ValidateFormat7Settings()

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

The current image settings are cached while validation is taking place. The cached settings are restored when validation is complete.

Parameters

| context | The fc2Context to be used. | |
|------------------|--|--|
| imageSettings | Structure containing the image settings. | |
| settingsAreValid | Whether the settings are valid. | |
| packetInfo | Packet size information that can be used to determine a valid packet size. | |

Returns

6.12 GVCP Register Operation

These functions deal with GVCP register operation on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegister (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register.

FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register with broadcast.

FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegister (fc2Context context, unsigned int address, unsigned int *pValue)

Read a GVCP register.

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBlock (fc2Context context, unsigned int address, const unsigned int *pBuffer, unsigned int length)

Write a GVCP register block.

FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegisterBlock (fc2Context context, unsigned int address, unsigned int *pBuffer, unsigned int length)

Read a GVCP register block.

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPMemory (fc2Context context, unsigned int address, const unsigned char *pBuffer, unsigned int length)

Write a GVCP memory block.

 FLYCAPTURE2_C_API fc2Error fc2ReadGVCPMemory (fc2Context context, unsigned int address, unsigned char *pBuffer, unsigned int length)

Read a GVCP memory block.

6.12.1 Detailed Description

These functions deal with GVCP register operation on the camera.

6.12.2 Function Documentation

6.12.2.1 fc2ReadGVCPMemory()

Read a GVCP memory block.

Parameters

| context | The fc2Context to be used. | |
|---------|--------------------------------------|--|
| address | GVCP address to be read from. | |
| pBuffer | Array containing data to be written. | |
| length | Size of array, in quadlets. | |

Returns

An Error indicating the success or failure of the function.

6.12.2.2 fc2ReadGVCPRegister()

Read a GVCP register.

Parameters

| context | The fc2Context to be used. |
|---------|-------------------------------|
| address | GVCP address to be read from. |
| pValue | The value that is read. |

Returns

An Error indicating the success or failure of the function.

6.12.2.3 fc2ReadGVCPRegisterBlock()

Read a GVCP register block.

| context | The fc2Context to be used. | |
|---------|--------------------------------------|--|
| address | GVCP address to be read from. | |
| pBuffer | Array containing data to be written. | |
| length | Size of array, in quadlets. | |

Returns

An Error indicating the success or failure of the function.

6.12.2.4 fc2WriteGVCPMemory()

Write a GVCP memory block.

Parameters

| context | The fc2Context to be used. | |
|---------|--------------------------------------|--|
| address | GVCP address to be write to. | |
| pBuffer | Array containing data to be written. | |
| length | Size of array, in quadlets. | |

Returns

An Error indicating the success or failure of the function.

6.12.2.5 fc2WriteGVCPRegister()

Write a GVCP register.

Parameters

| context | The fc2Context to be used. |
|---------|--------------------------------|
| address | GVCP address to be written to. |
| value | The value to be written. |

Returns

6.12.2.6 fc2WriteGVCPRegisterBlock()

Write a GVCP register block.

Parameters

| context | The fc2Context to be used. | |
|---------|--------------------------------------|--|
| address | GVCP address to be write to. | |
| pBuffer | Array containing data to be written. | |
| length | Size of array, in quadlets. | |

Returns

An Error indicating the success or failure of the function.

6.12.2.7 fc2WriteGVCPRegisterBroadcast()

Write a GVCP register with broadcast.

Parameters

| context | The fc2Context to be used. |
|---------|--------------------------------|
| address | GVCP address to be written to. |
| value | The value to be written. |

Returns

6.13 GigE property manipulation

These functions deal with GigE properties.

Functions

- FLYCAPTURE2_C_API fc2Error fc2GetGigEProperty (fc2Context context, fc2GigEProperty *pGigEProp)

 Get the specified GigEProperty.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEProperty (fc2Context context, const fc2GigEProperty *pGigE←
 Prop)

Set the specified GigEProperty.

• FLYCAPTURE2_C_API fc2Error fc2DiscoverGigEPacketSize (fc2Context context, unsigned int *packetSize)

Discover the largest packet size that works for the network link between the PC and the camera.

6.13.1 Detailed Description

These functions deal with GigE properties.

6.13.2 Function Documentation

6.13.2.1 fc2DiscoverGigEPacketSize()

Discover the largest packet size that works for the network link between the PC and the camera.

This is useful in cases where there may be multiple links between the PC and the camera and there is a possibility of a component not supporting the recommended jumbo frame packet size of 9000.

Parameters

| context | The fc2Context to be used. |
|------------|--|
| packetSize | The maximum packet size supported by the link. |

Returns

6.13.2.2 fc2GetGigEProperty()

Get the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

Parameters

| context | The fc2Context to be used. |
|-----------|----------------------------|
| pGigEProp | The GigE property to get. |

Returns

An Error indicating the success or failure of the function.

6.13.2.3 fc2SetGigEProperty()

Set the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

Parameters

| context | The fc2Context to be used. |
|-----------|----------------------------|
| pGigEProp | The GigE property to set. |

Returns

6.14 GigE image settings

These functions deal with GigE image setting.

Functions

 FLYCAPTURE2_C_API fc2Error fc2QueryGigElmagingMode (fc2Context context, fc2Mode mode, BOOL *isSupported)

Check if the particular imaging mode is supported by the camera.

- FLYCAPTURE2_C_API fc2Error fc2GetGigEImagingMode (fc2Context context, fc2Mode *mode)

 Get the current imaging mode on the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEImagingMode (fc2Context context, fc2Mode mode)

Set the current imaging mode to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettingsInfo (fc2Context context, fc2GigEImage
 SettingsInfo *pInfo)

Get information about the image settings possible on the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettings (fc2Context context, fc2GigEImageSettings *p↔
ImageSettings)

Get the current image settings on the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetGigEImageSettings (fc2Context context, const fc2GigEImageSettings *pImageSettings)

Set the image settings specified to the camera.

6.14.1 Detailed Description

These functions deal with GigE image setting.

6.14.2 Function Documentation

6.14.2.1 fc2GetGigEImageSettings()

```
\label{eq:flycapture2_c_api fc2} FLYCAPTURE2\_C\_API fc2Error fc2GetGigEImageSettings \ ( fc2Context \ context, fc2GigEImageSettings * pImageSettings \ )
```

Get the current image settings on the camera.

| context | The fc2Context to be used. |
|----------------|-----------------------------------|
| plmageSettings | Current image settings on camera. |

Returns

An Error indicating the success or failure of the function.

6.14.2.2 fc2GetGigEImageSettingsInfo()

```
\label{eq:flycapture2_c_api fc2} FLYCAPTURE2\_c\_API fc2Error fc2GetGigEImageSettingsInfo ( \\ fc2Context context, \\ fc2GigEImageSettingsInfo * pInfo )
```

Get information about the image settings possible on the camera.

Parameters

| context | The fc2Context to be used. |
|---------|-----------------------------|
| pInfo | Image settings information. |

Returns

An Error indicating the success or failure of the function.

6.14.2.3 fc2GetGigEImagingMode()

Get the current imaging mode on the camera.

Parameters

| context | The fc2Context to be used. |
|---------|-------------------------------------|
| mode | Current imaging mode on the camera. |

Returns

An Error indicating the success or failure of the function.

6.14.2.4 fc2QueryGigElmagingMode()

```
fc2Mode mode,
BOOL * isSupported )
```

Check if the particular imaging mode is supported by the camera.

Parameters

| context | The fc2Context to be used. |
|-------------|--------------------------------|
| mode | The mode to check. |
| isSupported | Whether the mode is supported. |

Returns

An Error indicating the success or failure of the function.

6.14.2.5 fc2SetGigEImageSettings()

```
FLYCAPTURE2_C_API fc2Error fc2SetGigEImageSettings ( fc2Context\ context, const\ fc2GigEImageSettings\ *\ pImageSettings\ )
```

Set the image settings specified to the camera.

Parameters

| context | The fc2Context to be used. |
|----------------|----------------------------------|
| pImageSettings | Image settings to set to camera. |

Returns

An Error indicating the success or failure of the function.

6.14.2.6 fc2SetGigEImagingMode()

Set the current imaging mode to the camera.

This should only be done when the camera is not streaming images.

| context | The fc2Context to be used. |
|---------|------------------------------------|
| mode | Imaging mode to set to the camera. |

6.15 GigE image binning settings

These functions deal with GigE image binning settings.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetGigEImageBinningSettings (fc2Context context, unsigned int *horz ← BinnningValue, unsigned int *vertBinnningValue)

Get the current binning settings on the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetGigEImageBinningSettings (fc2Context context, unsigned int horz → BinnningValue, unsigned int vertBinnningValue)

Set the specified binning values to the camera.

6.15.1 Detailed Description

These functions deal with GigE image binning settings.

6.15.2 Function Documentation

6.15.2.1 fc2GetGigEImageBinningSettings()

Get the current binning settings on the camera.

Parameters

| context | The fc2Context to be used. |
|-------------------|-----------------------------------|
| horzBinnningValue | Current horizontal binning value. |
| vertBinnningValue | Current vertical binning value. |

Returns

An Error indicating the success or failure of the function.

6.15.2.2 fc2SetGigEImageBinningSettings()

```
unsigned int horzBinnningValue,
unsigned int vertBinnningValue )
```

Set the specified binning values to the camera.

It is recommended that GetGigEImageSettingsInfo() be called after this function succeeds to retrieve the new image settings information for the new binning mode.

Parameters

| context | The fc2Context to be used. |
|-------------------|----------------------------|
| horzBinnningValue | Horizontal binning value. |
| vertBinnningValue | Vertical binning value. |

Returns

6.16 GigE image stream configuration

These functions deal with GigE image stream configuration.

Functions

FLYCAPTURE2_C_API fc2Error fc2GetNumStreamChannels (fc2Context context, unsigned int *num← Channels)

Get the number of stream channels present on the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel *pChannel)

Get the stream channel information for the specified channel.

• FLYCAPTURE2_C_API fc2Error fc2SetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel *pChannel)

Set the stream channel information for the specified channel.

- FLYCAPTURE2_C_API fc2Error fc2GetGigEConfig (fc2Context context, fc2GigEConfig *pConfig)

 Get the current gige config on the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEConfig (fc2Context context, const fc2GigEConfig *pConfig)

 Set the gige config specified to the camera.

6.16.1 Detailed Description

These functions deal with GigE image stream configuration.

6.16.2 Function Documentation

6.16.2.1 fc2GetGigEConfig()

Get the current gige config on the camera.

Parameters

| context | The fc2Context to be used. |
|-------------|----------------------------------|
| pGigEConfig | Current configuration on camera. |

Returns

6.16.2.2 fc2GetGigEStreamChannelInfo()

Get the stream channel information for the specified channel.

Parameters

| context | The fc2Context to be used. |
|----------|---|
| channel | Channel number to use. |
| pChannel | Stream channel information for the specified channel. |

Returns

An Error indicating the success or failure of the function.

6.16.2.3 fc2GetNumStreamChannels()

Get the number of stream channels present on the camera.

Parameters

| context | The fc2Context to be used. |
|-------------|------------------------------------|
| numChannels | Number of stream channels present. |

Returns

An Error indicating the success or failure of the function.

6.16.2.4 fc2SetGigEConfig()

Set the gige config specified to the camera.

Parameters

| context | The fc2Context to be used. |
|-------------|---------------------------------|
| pGigEConfig | configuration to set to camera. |

Returns

An Error indicating the success or failure of the function.

6.16.2.5 fc2SetGigEStreamChannelInfo()

Set the stream channel information for the specified channel.

Note that the source UDP port of the stream channel is read-only.

Parameters

| context | The fc2Context to be used. |
|----------|--|
| channel | Channel number to use. |
| pChannel | Stream channel information to use for the specified channel. |

Returns

6.17 Image Operation 85

6.17 Image Operation

The Image operations are used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

Functions

FLYCAPTURE2_C_API fc2Error fc2SetDefaultColorProcessing (fc2ColorProcessingAlgorithm default
 — Method)

Set the default color processing algorithm.

FLYCAPTURE2_C_API fc2Error fc2GetDefaultColorProcessing (fc2ColorProcessingAlgorithm *pDefault←
Method)

Get the default color processing algorithm.

• FLYCAPTURE2 C API fc2Error fc2SetDefaultOutputFormat (fc2PixelFormat format)

Set the default output pixel format.

• FLYCAPTURE2_C_API fc2Error fc2GetDefaultOutputFormat (fc2PixelFormat *pFormat)

Get the default output pixel format.

FLYCAPTURE2_C_API fc2Error fc2DetermineBitsPerPixel (fc2PixelFormat format, unsigned int *pBitsPer
 —
 Pixel)

Calculate the bits per pixel for the specified pixel format.

• FLYCAPTURE2_C_API fc2Error fc2CreateImage (fc2Image *pImage)

Create a fc2Image.

• FLYCAPTURE2_C_API fc2Error fc2DestroyImage (fc2Image *image)

Destroy the fc2Image.

• FLYCAPTURE2_C_API fc2Error fc2SetImageDimensions (fc2Image *pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

FLYCAPTURE2_C_API fc2Error fc2GetImageDimensions (fc2Image *pImage, unsigned int *pRows, unsigned int *pCols, unsigned int *pStride, fc2PixelFormat *pPixelFormat, fc2BayerTileFormat *pBayerFormat)

Get the image dimensions associated with the image object.

FLYCAPTURE2_C_API fc2Error fc2SetImageColorProcessing (fc2Image *pImage, fc2ColorProcessing ← Algorithm colorProc)

Set the color processing algorithm.

FLYCAPTURE2_C_API fc2Error fc2GetImageColorProcessing (fc2Image *pImage, fc2ColorProcessing ← Algorithm *pColorProc)

Get the current color processing algorithm.

• FLYCAPTURE2_C_API fc2Error fc2SetImageData (fc2Image *pImage, const unsigned char *pData, unsigned int dataSize)

Set the data of the Image object.

• FLYCAPTURE2_C_API fc2Error fc2GetImageData (fc2Image *pImage, unsigned char **ppData)

Get a pointer to the data associated with the image.

FLYCAPTURE2_C_API fc2Error fc2GetImageMetadata (fc2Image *pImage, fc2ImageMetadata *pImage ← MetaData)

Get the metadata associated with the image.

• FLYCAPTURE2 C API fc2TimeStamp fc2GetImageTimeStamp (fc2Image *pImage)

Get the timestamp data associated with the image.

FLYCAPTURE2_C_API fc2Error fc2SaveImage (fc2Image *pImage, const char *pFilename, fc2ImageFile←
 Format format)

Save the image to the specified file name with the file format specified.

• FLYCAPTURE2_C_API fc2Error fc2SaveImageWithOption (fc2Image *pImage, const char *pFilename, fc2ImageFileFormat format, void *pOption)

Save the image to the specified file name with the file format specified.

- FLYCAPTURE2_C_API fc2Error fc2ConvertImage (fc2Image *pImageIn, fc2Image *pImageOut)
- FLYCAPTURE2_C_API fc2Error fc2ConvertImageTo (fc2PixelFormat format, fc2Image *pImageIn, fc2Image *pImageOut)

Converts the current image buffer to the specified output format and stores the result in the specified image.

• FLYCAPTURE2_C_API fc2Error fc2CalculateImageStatistics (fc2Image *pImage, fc2ImageStatisticsContext *pImageStatisticsContext)

Calculate statistics associated with the image.

6.17.1 Detailed Description

The Image operations are used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

Operations on images are not guaranteed to be thread safe. It is recommended that operations on images be protected by thread synchronization constructs such as mutexes.

6.17.2 Function Documentation

6.17.2.1 fc2CalculateImageStatistics()

Calculate statistics associated with the image.

In order to collect statistics for a particular channel, the enabled flag for the channel must be set to true. Statistics can only be collected for images in Mono8, Mono16, RGB, RGBU, BGR and BGRU.

Parameters

| plmage | The fc2Image to be used. |
|-------------------------|---|
| plmageStatisticsContext | The fc2ImageStatisticsContext to hold the statistics. |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.2 fc2ConvertImage()

6.17 Image Operation 87

Parameters

| plmageIn | |
|-----------|--|
| plmageOut | |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.3 fc2ConvertImageTo()

Converts the current image buffer to the specified output format and stores the result in the specified image.

The destination image does not need to be configured in any way before the call is made.

Parameters

| format | Output format of the converted image. |
|-----------|---------------------------------------|
| plmageln | Input image. |
| plmageOut | Output image. |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.4 fc2CreateImage()

Create a fc2lmage.

If externally allocated memory is to be used for the converted image, simply assigning the pData member of the fc2lmage structure is insufficient. fc2SetImageData() should be called in order to populate the fc2lmage structure correctly.

See also

fc2SetImageData()

Parameters

| plmage Pointer to image to I | be created. |
|------------------------------|-------------|
|------------------------------|-------------|

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.5 fc2DestroyImage()

Destroy the fc2lmage.

Parameters

| image | Pointer to image to be destroyed. |
|-------|-----------------------------------|
|-------|-----------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.6 fc2DetermineBitsPerPixel()

Calculate the bits per pixel for the specified pixel format.

Parameters

| format | The pixel format. |
|---------------|---------------------|
| pBitsPerPixel | The bits per pixel. |

Returns

6.17 Image Operation 89

6.17.2.7 fc2GetDefaultColorProcessing()

```
\label{eq:flycapture2_c_api fc2} FLYCAPTURE2\_C\_API \ \ fc2Error \ \ fc2GetDefaultColorProcessing \ \ (  fc2ColorProcessingAlgorithm * pDefaultMethod \ )
```

Get the default color processing algorithm.

Parameters

| pDefaultMethod | The default color processing algorithm. |
|----------------|---|
|----------------|---|

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.8 fc2GetDefaultOutputFormat()

Get the default output pixel format.

Parameters

| pFormat | The default pixel format. |
|---------|---------------------------|
|---------|---------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.9 fc2GetImageColorProcessing()

Get the current color processing algorithm.

| plmage | The fc2Image to be used. |
|---------|--------------------------|
| piinaye | The lozimage to be used. |

See also

fc2SetColorProcessing()

Returns

The current color processing algorithm.

6.17.2.10 fc2GetImageData()

Get a pointer to the data associated with the image.

This function is considered unsafe. The pointer returned could be invalidated if the buffer is resized or released. The pointer may also be invalidated if the Image object is passed to fc2RetrieveBuffer().

Parameters

| plmage | The fc2Image to be used. |
|--------|------------------------------|
| ppData | A pointer to the image data. |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.11 fc2GetImageDimensions()

```
FLYCAPTURE2_C_API fc2Error fc2GetImageDimensions (
    fc2Image * pImage,
    unsigned int * pRows,
    unsigned int * pCols,
    unsigned int * pStride,
    fc2PixelFormat * pPixelFormat,
    fc2BayerTileFormat * pBayerFormat )
```

Get the image dimensions associated with the image object.

| plmage | The fc2lmage to be used. |
|--------------|--------------------------|
| pRows | Number of rows. |
| pCols | Number of columns. |
| pStride | The stride. |
| pPixelFormat | Pixel format. |
| pBayerFormat | Bayer tile format. |

6.17 Image Operation 91

6.17.2.12 fc2GetImageMetadata()

Get the metadata associated with the image.

This includes embedded image information.

Parameters

```
plmage The fc2Image to be used.
```

Returns

Metadata associated with the image.

6.17.2.13 fc2GetImageTimeStamp()

```
FLYCAPTURE2_C_API fc2TimeStamp fc2GetImageTimeStamp (  fc2Image * pImage )
```

Get the timestamp data associated with the image.

Parameters

```
plmage The fc2Image to be used.
```

Returns

Timestamp data associated with the image.

6.17.2.14 fc2SaveImage()

Save the image to the specified file name with the file format specified.

Parameters

| plmage | The fc2Image to be used. |
|-----------|------------------------------|
| pFilename | Filename to save image with. |
| format | File format to save in. |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.15 fc2SaveImageWithOption()

Save the image to the specified file name with the file format specified.

Parameters

| plmage | The fc2Image to be used. |
|-----------|------------------------------|
| pFilename | Filename to save image with. |
| format | File format to save in. |
| pOption | Options for saving image. |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.16 fc2SetDefaultColorProcessing()

```
\label{eq:flycontrol} FLYCAPTURE2\_C\_API \ fc2Error \ fc2SetDefaultColorProcessing \ ( \\ fc2ColorProcessingAlgorithm \ defaultMethod \ )
```

Set the default color processing algorithm.

This method will be used for any image with the DEFAULT algorithm set. The method used is determined at the time of the Convert() call, therefore the most recent execution of this function will take precedence. The default setting is shared within the current process.

| defaultMethod | The color processing algorithm to set. |
|---------------|--|
|---------------|--|

6.17 Image Operation 93

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.17 fc2SetDefaultOutputFormat()

Set the default output pixel format.

This format will be used for any call to Convert() that does not specify an output format. The format used will be determined at the time of the Convert() call, therefore the most recent execution of this function will take precedence. The default is shared within the current process.

Parameters

| format | The output pixel format to set. |
|--------|---------------------------------|
|--------|---------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.18 fc2SetImageColorProcessing()

Set the color processing algorithm.

This should be set on the input image object.

Parameters

| plmage | The fc2Image to be used. |
|-----------|--|
| colorProc | The color processing algorithm to use. |

See also

fc2GetColorProcessing()

Returns

6.17.2.19 fc2SetImageData()

Set the data of the Image object.

Ownership of the image buffer is not transferred to the Image object. It is the user's responsibility to delete the buffer when it is no longer in use.

Parameters

| plmage | The fc2lmage to be used. |
|----------|------------------------------|
| pData | Pointer to the image buffer. |
| dataSize | Size of the image buffer. |

Returns

A fc2Error indicating the success or failure of the function.

6.17.2.20 fc2SetImageDimensions()

```
FLYCAPTURE2_C_API fc2Error fc2SetImageDimensions (
    fc2Image * pImage,
    unsigned int rows,
    unsigned int cols,
    unsigned int stride,
    fc2PixelFormat pixelFormat,
    fc2BayerTileFormat bayerFormat)
```

Sets the dimensions of the image object.

Parameters

| plmage | The fc2Image to be used. |
|-------------|---------------------------|
| rows | Number of rows to set. |
| cols | Number of cols to set. |
| stride | Stride to set. |
| pixelFormat | Pixel format to set. |
| bayerFormat | Bayer tile format to set. |

Returns

6.18 Image Statistics Operation

The Image Statistics operation provides the functionality for the user to collect image channel statistics.

Functions

FLYCAPTURE2_C_API fc2Error fc2CreateImageStatistics (fc2ImageStatisticsContext *pImageStatistics
 — Context)

Create a statistics context.

 FLYCAPTURE2_C_API fc2Error fc2DestroyImageStatistics (fc2ImageStatisticsContext imageStatistics← Context)

Destroy a statistics context.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableAll (fc2ImageStatisticsContext imageStatistics← Context)

Enable all channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsDisableAll (fc2ImageStatisticsContext imageStatistics
 — Context)

Disable all channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableGreyOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the grey channel.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableRGBOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the RGB channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableHSLOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the HSL channels.

FLYCAPTURE2_C_API fc2Error fc2GetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL *pEnabled)

Get the status of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2SetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled)

Set the status of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2GetChannelRange (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int *pMin, unsigned int *pMax)

Get the range of a statistics channel.

Get the range of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2GetChannelNumPixelValues (fc2ImageStatisticsContext image
 — StatisticsContext, fc2StatisticsChannel channel, unsigned int *pNumPixelValues)

Get the number of unique pixel values in the image.

• FLYCAPTURE2_C_API fc2Error fc2GetChannelMean (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, float *pPixelValueMean)

Get the mean of the image.

FLYCAPTURE2_C_API fc2Error fc2GetChannelHistogram (fc2ImageStatisticsContext imageStatisticsContext imageStatisticsContext

Get the histogram for the image.

FLYCAPTURE2_C_API fc2Error fc2GetImageStatistics (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int *pRangeMin, unsigned int *pRangeMax, unsigned int *pPixelValueMin, unsigned int *pPixelValueMax, unsigned int *pNumPixelValues, float *pPixelValueMean, int **ppHistogram)

Get all statistics for the image.

6.18.1 Detailed Description

The Image Statistics operation provides the functionality for the user to collect image channel statistics.

6.18.2 Function Documentation

6.18.2.1 fc2CreateImageStatistics()

```
\label{lem:flycapture2_C_API fc2Error fc2CreateImageStatistics (} fc2ImageStatisticsContext * pImageStatisticsContext )
```

Create a statistics context.

Parameters

```
plmageStatisticsContext A statistics context.
```

Returns

A fc2Error indicating the success or failure of the function.

6.18.2.2 fc2DestroyImageStatistics()

Destroy a statistics context.

Parameters

```
imageStatisticsContext A statistics context.
```

Returns

A fc2Error indicating the success or failure of the function.

6.18.2.3 fc2GetChannelHistogram()

```
fc2StatisticsChannel channel,
int ** ppHistogram )
```

Get the histogram for the image.

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|---|
| channel | The statistics channel. |
| ppHistogram | Pointer to an array containing the histogram. |

Returns

An Error indicating the success or failure of the function.

6.18.2.4 fc2GetChannelMean()

Get the mean of the image.

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|-------------------------|
| channel | The statistics channel. |
| pPixelValueMean | The mean of the image. |

Returns

An Error indicating the success or failure of the function.

6.18.2.5 fc2GetChannelNumPixelValues()

Get the number of unique pixel values in the image.

| imageStatisticsContext | A statistics context. |
|--------------------------------------|------------------------------------|
| channel | The statistics channel. |
| Generated by Doxygen pNumPixelValues | The number of unique pixel values. |

Returns

An Error indicating the success or failure of the function.

6.18.2.6 fc2GetChannelPixelValueRange()

Get the range of a statistics channel.

The values returned are the maximum values recorded for all pixels in the image.

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|--------------------------|
| channel | The statistics channel. |
| pPixelValueMin | The minimum pixel value. |
| pPixelValueMax | The maximum pixel value. |

Returns

An Error indicating the success or failure of the function.

6.18.2.7 fc2GetChannelRange()

Get the range of a statistics channel.

The values returned are the maximum possible values for any given pixel in the image. This is generally 0-255 for 8 bit images, and 0-65535 for 16 bit images.

| imageStatisticsContext | A statistics context. |
|------------------------|-----------------------------|
| | |
| channel | The statistics channel. |
| onamor | The statistics orialino. |
| ρMin | The minimum possible value. |
| Piviii | The minimum possible value. |
| nMay | The mayimum pessible value |
| pMax | The maximum possible value. |

Returns

An Error indicating the success or failure of the function.

6.18.2.8 fc2GetChannelStatus()

Get the status of a statistics channel.

See also

fc2SetChannelStatus()

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|---------------------------------|
| channel | The statistics channel. |
| pEnabled | Whether the channel is enabled. |

Returns

An Error indicating the success or failure of the function.

6.18.2.9 fc2GetImageStatistics()

Get all statistics for the image.

| imageStatisticsContext | The statistics context. |
|------------------------|-----------------------------|
| channel | The statistics channel. |
| pRangeMin | The minimum possible value. |

Parameters

| pRangeMax | The maximum possible value. |
|-----------------|---|
| pPixelValueMin | The minimum pixel value. |
| pPixelValueMax | The maximum pixel value. |
| pNumPixelValues | The number of unique pixel values. |
| pPixelValueMean | The mean of the image. |
| ppHistogram | Pointer to an array containing the histogram. |

Returns

A fc2Error indicating the success or failure of the function.

6.18.2.10 fc2ImageStatisticsDisableAll()

```
\label{lem:flycapture2_C_API fc2Error fc2ImageStatisticsDisableAll (} fc2ImageStatisticsContext \ \textit{imageStatisticsContext} \ )
```

Disable all channels.

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|-----------------------|
|------------------------|-----------------------|

Returns

An Error indicating the success or failure of the function.

6.18.2.11 fc2ImageStatisticsEnableAll()

```
\label{lem:flycapture2_C_API fc2Error fc2ImageStatisticsEnableAll (} fc2ImageStatisticsContext \ imageStatisticsContext \ )
```

Enable all channels.

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|-----------------------|

Returns

6.18.2.12 fc2ImageStatisticsEnableGreyOnly()

```
\label{lem:flycapture2_c_api fc2} FLYCAPTURE2\_C\_API fc2\\ Error fc2\\ ImageStatisticsContext imageStatisticsContext )
```

Enable only the grey channel.

Parameters

```
imageStatisticsContext A statistics context.
```

Returns

An Error indicating the success or failure of the function.

6.18.2.13 fc2ImageStatisticsEnableHSLOnly()

```
\label{lem:flat_context} FLYCAPTURE2\_C\_API fc2Error fc2ImageStatisticsEnableHSLOnly ( \\ fc2ImageStatisticsContext imageStatisticsContext )
```

Enable only the HSL channels.

Parameters

```
imageStatisticsContext A statistics context.
```

Returns

An Error indicating the success or failure of the function.

6.18.2.14 fc2ImageStatisticsEnableRGBOnly()

Enable only the RGB channels.

Parameters

```
imageStatisticsContext | A statistics context.
```

Returns

6.18.2.15 fc2SetChannelStatus()

Set the status of a statistics channel.

See also

fc2GetChannelStatus()

Parameters

| imageStatisticsContext | A statistics context. |
|------------------------|--|
| channel | The statistics channel. |
| enabled | Whether the channel should be enabled. |

Returns

6.19 TopologyNode Operation

The TopologyNode operation provides the functionality for the user to generate a tree structure of all cameras and devices connected to a computer.

Functions

FLYCAPTURE2_C_API fc2Error fc2CreateTopologyNode (fc2TopologyNodeContext *pTopologyNode ← Context)

Create a TopologyNode context.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetGuid (fc2TopologyNodeContext TopologyNode
 — Context, fc2PGRGuid *pGuid)

Get the PGRGuid associated with the node.

Get the device ID associated with the node.

Get the node type associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetInterfaceType (fc2TopologyNodeContext Topology
 — NodeContext, fc2InterfaceType *pInterfaceType)

Get the interface type associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetNumChildren (fc2TopologyNodeContext Topology
 — NodeContext, unsigned int *pNumChildNodes)

Get the number of child nodes.

• FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeContext)

Context, unsigned int position, fc2TopologyNodeContext *pChildTopologyNodeContext)

Get child node located at the specified position.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeAddChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeContext)

Add the specified TopologyNode as a child of the node.

Get the number of ports.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetPortType (fc2TopologyNodeContext TopologyNode
 — Context, unsigned int position, fc2PortType *pPortType)

Get type of port located at the specified position.

Add the specified PortType as a port of the node.

FLYCAPTURE2_C_API BOOL fc2TopologyNodeAssignGuidToNode (fc2TopologyNodeContext Topology
 — NodeContext, fc2PGRGuid guid, int deviceId)

Assign a PGRGuid and device ID to the node.

FLYCAPTURE2_C_API BOOL fc2TopologyNodeAssignGuidToNodeEx (fc2TopologyNodeContext Topology
 — NodeContext, fc2PGRGuid guid, int deviceId, fc2NodeType nodeType)

Assign a PGRGuid, device ID and nodeType to the node.

FLYCAPTURE2_C_API fc2Error fc2DestroyTopologyNode (fc2TopologyNodeContext TopologyNodeContext)
 Destroy a TopologyNode context.

6.19.1 Detailed Description

The TopologyNode operation provides the functionality for the user to generate a tree structure of all cameras and devices connected to a computer.

6.19.2 Function Documentation

6.19.2.1 fc2CreateTopologyNode()

Create a TopologyNode context.

Parameters

| pTopologyNodeContext A Topology |
|-----------------------------------|
|-----------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.2 fc2DestroyTopologyNode()

Destroy a TopologyNode context.

Parameters

| TopologyNodeContext | A Topology Node context. |
|---------------------|--------------------------|
|---------------------|--------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.3 fc2TopologyNodeAddChild()

Add the specified TopologyNode as a child of the node.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|--------------------------|--|
| TopologyNodeChildContext | The TopologyNode child context to add. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.4 fc2TopologyNodeAddPortType()

Add the specified PortType as a port of the node.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| portType | childPort The port to add. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.5 fc2TopologyNodeAssignGuidToNode()

Assign a PGRGuid and device ID to the node.

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| guid | PGRGuid to be assigned. |
| deviceld | Device ID to be assigned. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.6 fc2TopologyNodeAssignGuidToNodeEx()

Assign a PGRGuid, device ID and nodeType to the node.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| guid | PGRGuid to be assigned. |
| deviceld | Device ID to be assigned. |
| nodeType | NodeType to be assigned |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.7 fc2TopologyNodeGetChild()

Get child node located at the specified position.

Parameters

| TopologyNodeContext | The Topology Node context to use. | |
|---------------------------|--|--|
| position | Position of the child node. | |
| pChildTopologyNodeContext | The Topology Node context the contains information on the child topology | |

Returns

6.19.2.8 fc2TopologyNodeGetDeviceId()

```
\label{local_problem} FLYCAPTURE2\_C\_API \ fc2Error \ fc2TopologyNodeContext \ \textit{TopologyNodeContext,} \\ \text{int } *pID \ )
```

Get the device ID associated with the node.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| pID | Device ID of the node. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.9 fc2TopologyNodeGetGuid()

Get the PGRGuid associated with the node.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|---|
| pGuid | The unique identifier associated with the node. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.10 fc2TopologyNodeGetInterfaceType()

Get the interface type associated with the node.

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| pInterfaceType | Interface type of the node. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.11 fc2TopologyNodeGetNodeType()

Get the node type associated with the node.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| pNodeType | Node type of the node. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.12 fc2TopologyNodeGetNumChildren()

Get the number of child nodes.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| pNumChildNodes | Number of child nodes. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.13 fc2TopologyNodeGetNumPorts()

```
\label{eq:context} FLYCAPTURE2\_C\_API fc2Error fc2TopologyNodeGetNumPorts ( \\ fc2TopologyNodeContext TopologyNodeContext, \\ unsigned int *pNumPorts )
```

Get the number of ports.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-----------------------------------|
| pNumPorts | Number of ports. |

Returns

A fc2Error indicating the success or failure of the function.

6.19.2.14 fc2TopologyNodeGetPortType()

Get type of port located at the specified position.

Parameters

| TopologyNodeContext | The Topology Node context to use. |
|---------------------|-------------------------------------|
| position | Position of the port. |
| pPortType | PortType at the specified position. |

Returns

6.20 Utilities

The utility operations are used to query for general system information such as operating system, available memory etc.

Functions

• FLYCAPTURE2_C_API fc2Error fc2CheckDriver (const fc2PGRGuid *pGuid)

Check for driver compatibility for the given camera guid.

Get the driver's name for a device.

• FLYCAPTURE2_C_API fc2Error fc2GetSystemInfo (fc2SystemInfo *pSystemInfo)

Get system information.

FLYCAPTURE2_C_API fc2Error fc2GetLibraryVersion (fc2Version *pVersion)

Get library version.

• FLYCAPTURE2_C_API fc2Error fc2LaunchBrowser (const char *pAddress)

Launch a URL in the system default browser.

• FLYCAPTURE2_C_API fc2Error fc2LaunchHelp (const char *pFileName)

Open a CHM file in the system default CHM viewer.

• FLYCAPTURE2_C_API fc2Error fc2LaunchCommand (const char *pCommand)

Execute a command in the terminal.

FLYCAPTURE2_C_API fc2Error fc2LaunchCommandAsync (const char *pCommand, fc2AsyncCommand
 — Callback pCallback, void *pUserData)

Execute a command in the terminal.

• FLYCAPTURE2_C_API const char * fc2ErrorToDescription (fc2Error error)

Get a string representation of an error.

6.20.1 Detailed Description

The utility operations are used to query for general system information such as operating system, available memory etc.

It can also be used to launch browsers, CHM viewers or terminal commands.

6.20.2 Function Documentation

6.20.2.1 fc2CheckDriver()

Check for driver compatibility for the given camera guid.

6.20 Utilities 111

Parameters

| pGuid | The PGRGuid of the device to check. |
|-------|-------------------------------------|
|-------|-------------------------------------|

Returns

FC2_ERROR_OK if the library is compatible with the currently loaded driver, otherwise an error indicating the type of failure.

6.20.2.2 fc2ErrorToDescription()

```
\label{eq:flycapture2_C_API const char* fc2ErrorToDescription (} fc2Error \ error \ )
```

Get a string representation of an error.

Parameters

| <i>error</i> Error to b | oe parsed. |
|-------------------------|------------|
|-------------------------|------------|

Returns

A fc2Error indicating the success or failure of the function.

6.20.2.3 fc2GetDriverDeviceName()

Get the driver's name for a device.

Parameters

| pGuid | The PGRGuid of the device to check. |
|-------------------|---|
| pDeviceName | The device name will be returned in this string |
| pDeviceNameLength | The length of the device name string returned |

Returns

6.20.2.4 fc2GetLibraryVersion()

```
\label{eq:flycapture2_c_api fc2Error fc2GetLibraryVersion (fc2Version * pVersion )} \\
```

Get library version.

Parameters

| pVersion Structure to receive the library version |
|---|
|---|

Returns

A fc2Error indicating the success or failure of the function.

6.20.2.5 fc2GetSystemInfo()

Get system information.

Parameters

| pSystemIr | ifo | Structure to receive system information. |
|-----------|-----|--|
|-----------|-----|--|

Returns

A fc2Error indicating the success or failure of the function.

6.20.2.6 fc2LaunchBrowser()

Launch a URL in the system default browser.

Parameters

| pAddress | URL to open in browser. |
|----------|-------------------------|

Returns

6.20 Utilities 113

6.20.2.7 fc2LaunchCommand()

Execute a command in the terminal.

This is a blocking call that will return when the command completes.

Parameters

| pCommand | Command to execute. |
|----------|---------------------|
| poommana | Command to oxocator |

Returns

A fc2Error indicating the success or failure of the function.

6.20.2.8 fc2LaunchCommandAsync()

Execute a command in the terminal.

This is a non-blocking call that will return immediately. The return value of the command can be retrieved in the callback.

Parameters

| pCommand | Command to execute. |
|-----------|--|
| pCallback | Callback to fire when command is complete. |
| pUserData | Data pointer to pass to callback. |

Returns

A fc2Error indicating the success or failure of the function.

6.20.2.9 fc2LaunchHelp()

Open a CHM file in the system default CHM viewer.

Parameters

| <i>pFileName</i> Fil | lename of CHM file to open. |
|----------------------|-----------------------------|
|----------------------|-----------------------------|

Returns

6.21 TypeDefs 115

6.21 TypeDefs

Data Structures

struct fc2PGRGuid

A GUID to the camera.

Macros

- #define FALSE 0
- #define TRUE 1
- #define FULL_32BIT_VALUE 0x7FFFFFF
- #define MAX_STRING_LENGTH 512

Typedefs

- · typedef int BOOL
- typedef void * fc2Context

A context to the FlyCapture2 C library.

typedef void * fc2GuiContext

A context to the FlyCapture2 C GUI library.

typedef void * fc2ImageImpl

An internal pointer used in the fc2Image structure.

typedef void * fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

typedef void * fc2TopologyNodeContext

A context referring to the TopologyNode object.

typedef void * fc2VideoContext

A context referring to the video recorder object.

6.21.1 Detailed Description

6.21.2 Macro Definition Documentation

6.21.2.1 FALSE

#define FALSE 0

6.21.2.2 FULL_32BIT_VALUE

#define FULL_32BIT_VALUE 0x7FFFFFF

6.21.2.3 MAX_STRING_LENGTH

```
#define MAX_STRING_LENGTH 512
```

6.21.2.4 TRUE

#define TRUE 1

6.21.3 Typedef Documentation

6.21.3.1 BOOL

typedef int BOOL

6.21.3.2 fc2Context

```
typedef void* fc2Context
```

A context to the FlyCapture2 C library.

It must be created before performing any calls to the library.

6.21.3.3 fc2GuiContext

```
typedef void* fc2GuiContext
```

A context to the FlyCapture2 C GUI library.

It must be created before performing any calls to the library.

6.21.3.4 fc2lmagelmpl

```
typedef void* fc2ImageImpl
```

An internal pointer used in the fc2Image structure.

6.21 TypeDefs 117

6.21.3.5 fc2ImageStatisticsContext

typedef void* fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

6.21.3.6 fc2TopologyNodeContext

typedef void* fc2TopologyNodeContext

A context referring to the TopologyNode object.

6.21.3.7 fc2VideoContext

typedef void* fc2VideoContext

A context referring to the video recorder object.

6.22 Enumerations

Enumerations

```
enum fc2Error {
 FC2 ERROR UNDEFINED = -1,
 FC2 ERROR OK,
 FC2 ERROR FAILED,
 FC2 ERROR NOT IMPLEMENTED,
 FC2_ERROR_FAILED_BUS_MASTER_CONNECTION,
 FC2_ERROR_NOT_CONNECTED,
 FC2 ERROR INIT FAILED,
 FC2 ERROR NOT INTITIALIZED,
 FC2_ERROR_INVALID_PARAMETER,
 FC2_ERROR_INVALID_SETTINGS,
 FC2 ERROR INVALID BUS MANAGER,
 FC2 ERROR MEMORY ALLOCATION FAILED,
 FC2 ERROR LOW LEVEL FAILURE,
 FC2 ERROR NOT FOUND,
 FC2 ERROR FAILED GUID.
 FC2_ERROR_INVALID_PACKET_SIZE,
 FC2_ERROR_INVALID_MODE,
 FC2_ERROR_NOT_IN_FORMAT7,
 FC2_ERROR_NOT_SUPPORTED,
 FC2_ERROR_TIMEOUT,
 FC2_ERROR_BUS_MASTER_FAILED,
 FC2 ERROR INVALID GENERATION,
 FC2 ERROR LUT_FAILED,
 FC2 ERROR IIDC FAILED,
 FC2 ERROR STROBE FAILED,
 FC2 ERROR TRIGGER FAILED,
 FC2 ERROR PROPERTY FAILED,
 FC2_ERROR_PROPERTY_NOT_PRESENT,
 FC2 ERROR REGISTER FAILED,
 FC2 ERROR READ REGISTER FAILED,
 FC2 ERROR WRITE REGISTER FAILED,
 FC2 ERROR ISOCH FAILED,
 FC2 ERROR ISOCH ALREADY STARTED,
 FC2 ERROR ISOCH NOT STARTED,
 FC2_ERROR_ISOCH_START_FAILED,
 FC2_ERROR_ISOCH_RETRIEVE_BUFFER_FAILED,
 FC2_ERROR_ISOCH_STOP_FAILED,
 FC2 ERROR ISOCH SYNC FAILED,
 FC2_ERROR_ISOCH_BANDWIDTH_EXCEEDED,
 FC2_ERROR_IMAGE_CONVERSION_FAILED,
 FC2_ERROR_IMAGE_LIBRARY_FAILURE,
 FC2_ERROR_BUFFER_TOO SMALL,
 FC2 ERROR IMAGE CONSISTENCY ERROR,
 FC2 ERROR INCOMPATIBLE DRIVER,
 FC2 ERROR FORCE 32BITS = FULL 32BIT VALUE }
    The error types returned by functions.

    enum fc2BusCallbackType {

 FC2 BUS RESET,
 FC2 ARRIVAL,
 FC2 REMOVAL
 FC2 CALLBACK TYPE FORCE 32BITS = FULL 32BIT VALUE }
    The type of bus callback to register a callback function for.
```

Generated by Doxygen

6.22 Enumerations 119

```
    enum fc2GrabMode {

 FC2 DROP FRAMES,
 FC2 BUFFER FRAMES,
 FC2_UNSPECIFIED_GRAB_MODE,
 FC2_GRAB_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    The grab strategy employed during image transfer.

    enum fc2GrabTimeout {

 FC2 TIMEOUT NONE = 0,
 FC2_TIMEOUT_INFINITE = -1,
 FC2_TIMEOUT_UNSPECIFIED = -2,
 FC2_GRAB_TIMEOUT_FORCE_32BITS = FULL_32BIT_VALUE }
    Timeout options for grabbing images.

    enum fc2BandwidthAllocation {

 FC2 BANDWIDTH ALLOCATION OFF = 0,
 FC2_BANDWIDTH_ALLOCATION_ON = 1,
 FC2_BANDWIDTH_ALLOCATION_UNSUPPORTED = 2,
 FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED = 3,
 FC2_BANDWIDTH_ALLOCATION_FORCE_32BITS = FULL_32BIT_VALUE }
    Bandwidth allocation options for 1394 devices.

    enum fc2InterfaceType {

 FC2_INTERFACE_IEEE1394,
 FC2_INTERFACE_USB_2,
 FC2_INTERFACE_USB_3,
 FC2_INTERFACE_GIGE,
 FC2_INTERFACE_UNKNOWN,
 FC2_INTERFACE_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Interfaces that a camera may use to communicate with a host.

    enum fc2PropertyType {

 FC2 BRIGHTNESS,
 FC2 AUTO EXPOSURE,
 FC2_SHARPNESS,
 FC2_WHITE_BALANCE,
 FC2 HUE,
 FC2 SATURATION,
 FC2_GAMMA,
 FC2 IRIS,
 FC2 FOCUS.
 FC2_ZOOM,
 FC2_PAN,
 FC2_TILT,
 FC2_SHUTTER,
 FC2 GAIN,
 FC2_TRIGGER_MODE,
 FC2 TRIGGER DELAY,
 FC2 FRAME RATE,
 FC2 TEMPERATURE,
 FC2 UNSPECIFIED PROPERTY TYPE,
 FC2_PROPERTY_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Camera properties.
enum fc2FrameRate {
 FC2_FRAMERATE_1_875,
 FC2_FRAMERATE_3_75,
 FC2 FRAMERATE 7 5,
 FC2 FRAMERATE 15,
 FC2 FRAMERATE 30,
 FC2_FRAMERATE_60,
 FC2_FRAMERATE_120,
```

```
FC2_FRAMERATE_240,
 FC2 FRAMERATE FORMAT7,
 FC2 NUM FRAMERATES,
 FC2_FRAMERATE_FORCE_32BITS = FULL_32BIT_VALUE }
    Frame rates in frames per second.
enum fc2VideoMode {
 FC2 VIDEOMODE 160x120YUV444,
 FC2 VIDEOMODE 320x240YUV422,
 FC2_VIDEOMODE_640x480YUV411,
 FC2_VIDEOMODE_640x480YUV422,
 FC2_VIDEOMODE_640x480RGB,
 FC2_VIDEOMODE_640x480Y8,
 FC2_VIDEOMODE_640x480Y16,
 FC2_VIDEOMODE_800x600YUV422,
 FC2 VIDEOMODE 800x600RGB,
 FC2 VIDEOMODE 800x600Y8,
 FC2_VIDEOMODE_800x600Y16,
 FC2_VIDEOMODE_1024x768YUV422,
 FC2_VIDEOMODE_1024x768RGB,
 FC2_VIDEOMODE_1024x768Y8,
 FC2_VIDEOMODE_1024x768Y16,
 FC2_VIDEOMODE_1280x960YUV422,
 FC2 VIDEOMODE 1280x960RGB,
 FC2 VIDEOMODE 1280x960Y8,
 FC2 VIDEOMODE 1280x960Y16,
 FC2 VIDEOMODE 1600x1200YUV422,
 FC2_VIDEOMODE_1600x1200RGB,
 FC2_VIDEOMODE_1600x1200Y8,
 FC2_VIDEOMODE_1600x1200Y16,
 FC2_VIDEOMODE_FORMAT7,
 FC2 NUM VIDEOMODES,
 FC2_VIDEOMODE_FORCE_32BITS = FULL_32BIT_VALUE }
    DCAM video modes.
enum fc2Mode {
 FC2 MODE 0 = 0,
 FC2 MODE 1,
 FC2 MODE 2,
 FC2_MODE_3,
 FC2_MODE_4,
 FC2 MODE 5,
 FC2 MODE_6,
 FC2 MODE 7,
 FC2 MODE 8,
 FC2 MODE 9,
 FC2_MODE_10,
 FC2_MODE_11,
 FC2_MODE_12,
 FC2 MODE 13,
 FC2_MODE_14,
 FC2_MODE_15,
 FC2 MODE 16,
 FC2_MODE_17,
 FC2_MODE_18,
 FC2 MODE 19,
 FC2 MODE 20,
 FC2 MODE 21,
 FC2_MODE_22,
 FC2_MODE_23,
```

6.22 Enumerations 121

```
FC2_MODE_24,
 FC2 MODE 25,
 FC2 MODE 26,
 FC2_MODE_27,
 FC2 MODE 28,
 FC2 MODE 29,
 FC2 MODE 30,
 FC2 MODE 31,
 FC2 NUM MODES,
 FC2_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    Camera modes for DCAM formats as well as Format7.
enum fc2PixelFormat {
 FC2_PIXEL_FORMAT_MONO8 = 0x80000000,
 FC2 PIXEL FORMAT 411YUV8 = 0x40000000,
 FC2_PIXEL_FORMAT_422YUV8 = 0x200000000,
 FC2_PIXEL_FORMAT_444YUV8 = 0x100000000,
 FC2 PIXEL FORMAT RGB8 = 0x08000000,
 FC2_PIXEL_FORMAT_MONO16 = 0x04000000,
 FC2_PIXEL_FORMAT_RGB16 = 0x020000000,
 FC2_PIXEL_FORMAT_S_MONO16 = 0x01000000,
 FC2 PIXEL FORMAT S RGB16 = 0x00800000,
 FC2_PIXEL_FORMAT_RAW8 = 0x00400000,
 FC2_PIXEL_FORMAT_RAW16 = 0x00200000,
 FC2_PIXEL_FORMAT_MONO12 = 0x00100000
 FC2 PIXEL FORMAT RAW12 = 0x00080000.
 FC2 PIXEL FORMAT BGR = 0x80000008,
 FC2 PIXEL FORMAT BGRU = 0x40000008,
 FC2 PIXEL FORMAT RGB = FC2 PIXEL FORMAT RGB8,
 FC2 PIXEL FORMAT RGBU = 0x40000002,
 FC2_PIXEL_FORMAT_BGR16 = 0x02000001,
 FC2_PIXEL_FORMAT_BGRU16 = 0x02000002,
 FC2_PIXEL_FORMAT_422YUV8_JPEG = 0x40000001,
 FC2 NUM PIXEL FORMATS = 20,
 FC2_UNSPECIFIED_PIXEL_FORMAT = 0 }
    Pixel formats available for Format7 modes.
enum fc2BusSpeed {
 FC2 BUSSPEED S100.
 FC2_BUSSPEED_S200,
 FC2_BUSSPEED_S400,
 FC2 BUSSPEED S480,
 FC2 BUSSPEED S800,
 FC2_BUSSPEED_S1600,
 FC2 BUSSPEED S3200,
 FC2 BUSSPEED S5000.
 FC2 BUSSPEED 10BASE T,
 FC2_BUSSPEED_100BASE_T,
 FC2_BUSSPEED_1000BASE_T,
 FC2 BUSSPEED 10000BASE T,
 FC2_BUSSPEED_S_FASTEST,
 FC2_BUSSPEED_ANY,
 FC2_BUSSPEED_SPEED_UNKNOWN = -1,
 FC2_BUSSPEED_FORCE_32BITS = FULL_32BIT_VALUE }
    Bus speeds.

    enum fc2PCleBusSpeed {

 FC2 PCIE BUSSPEED 2 5,
 FC2 PCIE BUSSPEED 5 0,
 FC2_PCIE_BUSSPEED_UNKNOWN = -1,
 FC2_PCIE_BUSSPEED_FORCE_32BITS = FULL_32BIT_VALUE }
```

```
enum fc2DriverType {
 FC2 DRIVER 1394 CAM,
 FC2_DRIVER_1394_PRO,
 FC2_DRIVER_1394_JUJU,
 FC2_DRIVER_1394_VIDEO1394,
 FC2 DRIVER 1394 RAW1394,
 FC2 DRIVER USB NONE,
 FC2_DRIVER_USB_CAM,
 FC2 DRIVER USB3 PRO,
 FC2 DRIVER GIGE NONE,
 FC2_DRIVER_GIGE_FILTER,
 FC2_DRIVER_GIGE_PRO,
 FC2_DRIVER_GIGE_LWF,
 FC2 DRIVER UNKNOWN = -1,
 FC2_DRIVER_FORCE_32BITS = FULL_32BIT_VALUE }
    Types of low level drivers that FlyCapture uses.
• enum fc2ColorProcessingAlgorithm {
 FC2_DEFAULT,
 FC2 NO COLOR PROCESSING,
 FC2_NEAREST_NEIGHBOR_FAST,
 FC2_EDGE_SENSING,
 FC2_HQ_LINEAR,
 FC2 RIGOROUS,
 FC2 IPP,
 FC2 DIRECTIONAL,
 FC2 WEIGHTED DIRECTIONAL,
 FC2 COLOR PROCESSING ALGORITHM FORCE 32BITS = FULL 32BIT VALUE }
    Color processing algorithms.
enum fc2BayerTileFormat {
 FC2_BT_NONE,
 FC2_BT_RGGB,
 FC2 BT GRBG,
 FC2 BT GBRG,
 FC2_BT_BGGR,
 FC2_BT_FORCE_32BITS = FULL_32BIT_VALUE }
    Bayer tile formats.

    enum fc2lmageFileFormat {

 FC2 FROM FILE EXT = -1,
 FC2 PGM,
 FC2 PPM,
 FC2 BMP,
 FC2 JPEG,
 FC2_JPEG2000,
 FC2_TIFF,
 FC2 PNG,
 FC2 RAW,
 FC2 IMAGE FILE FORMAT FORCE 32BITS = FULL 32BIT VALUE }
    File formats to be used for saving images to disk.
```

6.22.1 **Detailed Description**

6.22.2 Enumeration Type Documentation

6.22 Enumerations 123

6.22.2.1 fc2BandwidthAllocation

enum fc2BandwidthAllocation

Bandwidth allocation options for 1394 devices.

Enumerator

| FC2_BANDWIDTH_ALLOCATION_OFF | Do not allocate bandwidth. |
|---------------------------------------|---|
| FC2_BANDWIDTH_ALLOCATION_ON | Allocate bandwidth. This is the default setting. |
| FC2_BANDWIDTH_ALLOCATION_UNSUPPORTED | Bandwidth allocation is not supported by either the camera or operating system. |
| FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED | Not specified. This leaves the current setting unchanged. |
| FC2_BANDWIDTH_ALLOCATION_FORCE_32BITS | |

6.22.2.2 fc2BayerTileFormat

enum fc2BayerTileFormat

Bayer tile formats.

Enumerator

| FC2_BT_NONE | No bayer tile format. |
|---------------------|-----------------------|
| FC2_BT_RGGB | Red-Green-Green-Blue. |
| FC2_BT_GRBG | Green-Red-Blue-Green. |
| FC2_BT_GBRG | Green-Blue-Red-Green. |
| FC2_BT_BGGR | Blue-Green-Green-Red. |
| FC2_BT_FORCE_32BITS | |

6.22.2.3 fc2BusCallbackType

enum fc2BusCallbackType

The type of bus callback to register a callback function for.

| FC2_BUS_RESET | Register for all bus events. |
|--------------------------------|------------------------------|
| FC2_ARRIVAL | Register for arrivals only. |
| FC2_REMOVAL | Register for removals only. |
| FC2_CALLBACK_TYPE_FORCE_32BITS | |

6.22.2.4 fc2BusSpeed

enum fc2BusSpeed

Bus speeds.

Enumerator

| FC2_BUSSPEED_S100 | 100Mbits/sec. |
|----------------------------|---|
| FC2_BUSSPEED_S200 | 200Mbits/sec. |
| FC2_BUSSPEED_S400 | 400Mbits/sec. |
| FC2_BUSSPEED_S480 | 480Mbits/sec. Only for USB2 cameras. |
| FC2_BUSSPEED_S800 | 800Mbits/sec. |
| FC2_BUSSPEED_S1600 | 1600Mbits/sec. |
| FC2_BUSSPEED_S3200 | 3200Mbits/sec. |
| FC2_BUSSPEED_S5000 | 5000Mbits/sec. Only for USB3 cameras. |
| FC2_BUSSPEED_10BASE_T | 10Base-T. Only for GigE cameras. |
| FC2_BUSSPEED_100BASE_T | 100Base-T. Only for GigE cameras. |
| FC2_BUSSPEED_1000BASE_T | 1000Base-T (Gigabit Ethernet). Only for GigE cameras. |
| FC2_BUSSPEED_10000BASE_T | 10000Base-T. Only for GigE cameras. |
| FC2_BUSSPEED_S_FASTEST | The fastest speed available. |
| FC2_BUSSPEED_ANY | Any speed that is available. |
| FC2_BUSSPEED_SPEED_UNKNOWN | Unknown bus speed. |
| FC2_BUSSPEED_FORCE_32BITS | |
| | |

6.22.2.5 fc2ColorProcessingAlgorithm

 $\verb"enum" fc2ColorProcessingAlgorithm"$

Color processing algorithms.

Please refer to our knowledge base at article at http://www.ptgrey.com/support/kb/index. \leftarrow asp?a=4&q=33 for complete details for each algorithm.

| FC2_DEFAULT | Default method. |
|---------------------------|---|
| FC2_NO_COLOR_PROCESSING | No color processing. |
| FC2_NEAREST_NEIGHBOR_FAST | Fastest but lowest quality. Equivalent to FLYCAPTURE_NEAREST_NEIGHBOR_FAST in FlyCapture. |
| FC2_EDGE_SENSING | Weights surrounding pixels based on localized edge orientation. |
| FC2_HQ_LINEAR | Well-balanced speed and quality. |
| FC2_RIGOROUS | Slowest but produces good results. |

6.22 Enumerations 125

Enumerator

| FC2_IPP | Multithreaded with similar results to edge sensing. |
|-------------------------------------|---|
| FC2_DIRECTIONAL | Best quality but much faster than rigorous. |
| FC2_WEIGHTED_DIRECTIONAL | Weighted pixel average from different directions. |
| FC2_COLOR_PROCESSING_ALGORITHM_FOR← | |
| CE_32BITS | |

6.22.2.6 fc2DriverType

enum fc2DriverType

Types of low level drivers that FlyCapture uses.

Enumerator

| FC2_DRIVER_1394_CAM | PGRCam.sys. |
|---------------------------|---|
| FC2_DRIVER_1394_PRO | PGR1394.sys. |
| FC2_DRIVER_1394_JUJU | firewire_core. |
| FC2_DRIVER_1394_VIDEO1394 | video1394. |
| FC2_DRIVER_1394_RAW1394 | raw1394. |
| FC2_DRIVER_USB_NONE | No usb driver used just BSD stack. (Linux only) |
| FC2_DRIVER_USB_CAM | PGRUsbCam.sys. |
| FC2_DRIVER_USB3_PRO | PGRXHCI.sys. |
| FC2_DRIVER_GIGE_NONE | no GigE drivers used, MS/BSD stack. |
| FC2_DRIVER_GIGE_FILTER | PGRGigE.sys. |
| FC2_DRIVER_GIGE_PRO | PGRGigEPro.sys. |
| FC2_DRIVER_GIGE_LWF | PgrLwf.sys. |
| FC2_DRIVER_UNKNOWN | Unknown driver type. |
| FC2_DRIVER_FORCE_32BITS | |

6.22.2.7 fc2Error

enum fc2Error

The error types returned by functions.

| FC2_ERROR_UNDEFINED | Undefined. |
|--|------------------------------------|
| FC2_ERROR_OK | Function returned with no errors. |
| FC2_ERROR_FAILED | General failure. |
| FC2_ERROR_NOT_IMPLEMENTED | Function has not been implemented. |
| FC2_ERROR_FAILED_BUS_MASTER_CONNECTION | Could not connect to Bus Master. |

Enumerator

| FC2_ERROR_NOT_CONNECTED | Camera has not been connected. |
|--|--|
| FC2_ERROR_INIT_FAILED | Initialization failed. |
| FC2_ERROR_NOT_INTITIALIZED | Camera has not been initialized. |
| FC2_ERROR_INVALID_PARAMETER | Invalid parameter passed to function. |
| FC2_ERROR_INVALID_SETTINGS | Setting set to camera is invalid. |
| FC2_ERROR_INVALID_BUS_MANAGER | Invalid Bus Manager object. |
| FC2_ERROR_MEMORY_ALLOCATION_FAILED | Could not allocate memory. |
| FC2_ERROR_LOW_LEVEL_FAILURE | Low level error. |
| FC2_ERROR_NOT_FOUND | Device not found. |
| FC2_ERROR_FAILED_GUID | GUID failure. |
| FC2_ERROR_INVALID_PACKET_SIZE | Packet size set to camera is invalid. |
| FC2_ERROR_INVALID_MODE | Invalid mode has been passed to function. |
| FC2_ERROR_NOT_IN_FORMAT7 | Error due to not being in Format7. |
| FC2_ERROR_NOT_SUPPORTED | This feature is unsupported. |
| FC2_ERROR_TIMEOUT | Timeout error. |
| FC2_ERROR_BUS_MASTER_FAILED | Bus Master Failure. |
| FC2_ERROR_INVALID_GENERATION | Generation Count Mismatch. |
| FC2_ERROR_LUT_FAILED | Look Up Table failure. |
| FC2_ERROR_IIDC_FAILED | IIDC failure. |
| FC2_ERROR_STROBE_FAILED | Strobe failure. |
| FC2_ERROR_TRIGGER_FAILED | Trigger failure. |
| FC2_ERROR_PROPERTY_FAILED | Property failure. |
| FC2_ERROR_PROPERTY_NOT_PRESENT | Property is not present. |
| FC2_ERROR_REGISTER_FAILED | Register access failed. |
| FC2_ERROR_READ_REGISTER_FAILED | Register read failed. |
| FC2_ERROR_WRITE_REGISTER_FAILED | Register write failed. |
| FC2_ERROR_ISOCH_FAILED | Isochronous failure. |
| FC2_ERROR_ISOCH_ALREADY_STARTED | Isochronous transfer has already been started. |
| FC2_ERROR_ISOCH_NOT_STARTED | Isochronous transfer has not been started. |
| FC2_ERROR_ISOCH_START_FAILED | Isochronous start failed. |
| FC2_ERROR_ISOCH_RETRIEVE_BUFFER_FAILED | Isochronous retrieve buffer failed. |
| FC2_ERROR_ISOCH_STOP_FAILED | Isochronous stop failed. |
| FC2_ERROR_ISOCH_SYNC_FAILED | Isochronous image synchronization failed. |
| FC2_ERROR_ISOCH_BANDWIDTH_EXCEEDED | Isochronous bandwidth exceeded. |
| FC2_ERROR_IMAGE_CONVERSION_FAILED | Image conversion failed. |
| FC2_ERROR_IMAGE_LIBRARY_FAILURE | Image library failure. |
| FC2_ERROR_BUFFER_TOO_SMALL | Buffer is too small. |
| FC2_ERROR_IMAGE_CONSISTENCY_ERROR | There is an image consistency error. |
| FC2_ERROR_INCOMPATIBLE_DRIVER | The installed driver is not compatible with the library. |
| FC2 ERROR FORCE 32BITS | , |
| | |

6.22.2.8 fc2FrameRate

enum fc2FrameRate

Frame rates in frames per second.

6.22 Enumerations 127

Enumerator

| FC2_FRAMERATE_1_875 | 1.875 fps. |
|----------------------------|--|
| FC2_FRAMERATE_3_75 | 3.75 fps. |
| FC2_FRAMERATE_7_5 | 7.5 fps. |
| FC2_FRAMERATE_15 | 15 fps. |
| FC2_FRAMERATE_30 | 30 fps. |
| FC2_FRAMERATE_60 | 60 fps. |
| FC2_FRAMERATE_120 | 120 fps. |
| FC2_FRAMERATE_240 | 240 fps. |
| FC2_FRAMERATE_FORMAT7 | Custom frame rate for Format7 functionality. |
| FC2_NUM_FRAMERATES | Number of possible camera frame rates. |
| FC2_FRAMERATE_FORCE_32BITS | |

6.22.2.9 fc2GrabMode

enum fc2GrabMode

The grab strategy employed during image transfer.

This type controls how images that stream off the camera accumulate in a user buffer for handling.

Enumerator

| FC2_DROP_FRAMES | Grabs the newest image in the user buffer each time the RetrieveBuffer() function is called. Older images are dropped instead of accumulating in the user buffer. Grabbing blocks if the camera has not finished transmitting the next available image. If the camera is transmitting images faster than the application can grab them, images may be dropped and only the most recent image is stored for grabbing. Note that this mode is the equivalent of flycaptureLockLatest in earlier versions of the FlyCapture SDK. |
|----------------------------|--|
| FC2_BUFFER_FRAMES | Images accumulate in the user buffer, and the oldest image is grabbed for handling before being discarded. This member can be used to guarantee that each image is seen. However, image processing time must not exceed transmission time from the camera to the buffer. Grabbing blocks if the camera has not finished transmitting the next available image. The buffer size is controlled by the numBuffers parameter in the FC2Config struct. Note that this mode is the equivalent of flycaptureLockNext in earlier versions of the FlyCapture SDK. |
| FC2_UNSPECIFIED_GRAB_MODE | Unspecified grab mode. |
| FC2_GRAB_MODE_FORCE_32BITS | |

6.22.2.10 fc2GrabTimeout

enum fc2GrabTimeout

Timeout options for grabbing images.

Enumerator

| FC2_TIMEOUT_NONE | Non-blocking wait. |
|-------------------------------|------------------------------|
| FC2_TIMEOUT_INFINITE | Wait indefinitely. |
| FC2_TIMEOUT_UNSPECIFIED | Unspecified timeout setting. |
| FC2_GRAB_TIMEOUT_FORCE_32BITS | |

6.22.2.11 fc2ImageFileFormat

enum fc2ImageFileFormat

File formats to be used for saving images to disk.

Enumerator

| FC2_FROM_FILE_EXT | Determine file format from file extension. |
|------------------------------------|--|
| FC2_PGM | Portable gray map. |
| FC2_PPM | Portable pixmap. |
| FC2_BMP | Bitmap. |
| FC2_JPEG | JPEG. |
| FC2_JPEG2000 | JPEG 2000. |
| FC2_TIFF | Tagged image file format. |
| FC2_PNG | Portable network graphics. |
| FC2_RAW | Raw data. |
| FC2_IMAGE_FILE_FORMAT_FORCE_32BITS | |

6.22.2.12 fc2InterfaceType

enum fc2InterfaceType

Interfaces that a camera may use to communicate with a host.

| FC2_INTERFACE_IEEE1394 | IEEE-1394 (Includes 1394a and 1394b). |
|---------------------------------|---------------------------------------|
| FC2_INTERFACE_USB_2 | USB 2.0. |
| FC2_INTERFACE_USB_3 | USB 3.0. |
| FC2_INTERFACE_GIGE | GigE. |
| FC2_INTERFACE_UNKNOWN | Unknown interface. |
| FC2_INTERFACE_TYPE_FORCE_32BITS | |

6.22 Enumerations 129

6.22.2.13 fc2Mode

enum fc2Mode

Camera modes for DCAM formats as well as Format7.

Enumerator

| FC2_MODE_0 FC2_MODE_1 FC2_MODE_2 FC2_MODE_3 FC2_MODE_4 FC2_MODE_5 FC2_MODE_6 FC2_MODE_7 FC2_MODE_8 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_15 FC2_MODE_15 FC2_MODE_15 FC2_MODE_16 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_5 FC2_MODE_31 FC2_MODE_5 FC2_FC2_FC2_FC2 FC2_FC2_FC2_FC2_FC2 FC2_FC2_FC2_FC2 FC2_FC2_FC2_FC2_FC2 FC2_FC2_FC2_FC2 FC2_FC2_FC2_FC2 | | |
|---|-----------------------|------------------|
| FC2_MODE_2 FC2_MODE_3 FC2_MODE_4 FC2_MODE_5 FC2_MODE_6 FC2_MODE_7 FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_15 FC2_MODE_16 FC2_MODE_16 FC2_MODE_17 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_S Number of modes. | FC2_MODE_0 | |
| FC2_MODE_3 FC2_MODE_4 FC2_MODE_5 FC2_MODE_6 FC2_MODE_7 FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_S | FC2_MODE_1 | |
| FC2_MODE_4 FC2_MODE_5 FC2_MODE_6 FC2_MODE_7 FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_2 | |
| FC2_MODE_5 FC2_MODE_6 FC2_MODE_7 FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_11 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_3 | |
| FC2_MODE_6 FC2_MODE_7 FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 | FC2_MODE_4 | |
| FC2_MODE_7 FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_S | FC2_MODE_5 | |
| FC2_MODE_8 FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_16 FC2_MODE_17 FC2_MODE_19 FC2_MODE_20 FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 | FC2_MODE_6 | |
| FC2_MODE_9 FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_16 FC2_MODE_17 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_7 | |
| FC2_MODE_10 FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_17 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_8 | |
| FC2_MODE_11 FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_9 | |
| FC2_MODE_12 FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_10 | |
| FC2_MODE_13 FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_11 | |
| FC2_MODE_14 FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_12 | |
| FC2_MODE_15 FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_13 | |
| FC2_MODE_16 FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_14 | |
| FC2_MODE_17 FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_15 | |
| FC2_MODE_18 FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_16 | |
| FC2_MODE_19 FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_17 | |
| FC2_MODE_20 FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_26 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_18 | |
| FC2_MODE_21 FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_19 | |
| FC2_MODE_22 FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_20 | |
| FC2_MODE_23 FC2_MODE_24 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_21 | |
| FC2_MODE_24 FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_22 | |
| FC2_MODE_25 FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_23 | |
| FC2_MODE_26 FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_24 | |
| FC2_MODE_27 FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_25 | |
| FC2_MODE_28 FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_26 | |
| FC2_MODE_29 FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_27 | |
| FC2_MODE_30 FC2_MODE_31 FC2_NUM_MODES Number of modes. | FC2_MODE_28 | |
| FC2_NUM_MODES Number of modes. | FC2_MODE_29 | |
| FC2_NUM_MODES Number of modes. | FC2_MODE_30 | |
| | FC2_MODE_31 | |
| FC2_MODE_FORCE_32BITS | FC2_NUM_MODES | Number of modes. |
| | FC2_MODE_FORCE_32BITS | |

6.22.2.14 fc2PCleBusSpeed

enum fc2PCIeBusSpeed

Enumerator

| FC2_PCIE_BUSSPEED_2_5 | |
|--------------------------------|-------------------|
| FC2_PCIE_BUSSPEED_5_0 | 2.5 Gb/s |
| FC2_PCIE_BUSSPEED_UNKNOWN | 5.0 Gb/s |
| FC2_PCIE_BUSSPEED_FORCE_32BITS | Speed is unknown. |

6.22.2.15 fc2PixelFormat

enum fc2PixelFormat

Pixel formats available for Format7 modes.

Enumerator

| FC2_PIXEL_FORMAT_MONO8 | 8 bits of mono information. |
|-------------------------------|-------------------------------------|
| FC2_PIXEL_FORMAT_411YUV8 | YUV 4:1:1. |
| FC2_PIXEL_FORMAT_422YUV8 | YUV 4:2:2. |
| FC2_PIXEL_FORMAT_444YUV8 | YUV 4:4:4. |
| FC2_PIXEL_FORMAT_RGB8 | R = G = B = 8 bits. |
| FC2_PIXEL_FORMAT_MONO16 | 16 bits of mono information. |
| FC2_PIXEL_FORMAT_RGB16 | R = G = B = 16 bits. |
| FC2_PIXEL_FORMAT_S_MONO16 | 16 bits of signed mono information. |
| FC2_PIXEL_FORMAT_S_RGB16 | R = G = B = 16 bits signed. |
| FC2_PIXEL_FORMAT_RAW8 | 8 bit raw data output of sensor. |
| FC2_PIXEL_FORMAT_RAW16 | 16 bit raw data output of sensor. |
| FC2_PIXEL_FORMAT_MONO12 | 12 bits of mono information. |
| FC2_PIXEL_FORMAT_RAW12 | 12 bit raw data output of sensor. |
| FC2_PIXEL_FORMAT_BGR | 24 bit BGR. |
| FC2_PIXEL_FORMAT_BGRU | 32 bit BGRU. |
| FC2_PIXEL_FORMAT_RGB | 24 bit RGB. |
| FC2_PIXEL_FORMAT_RGBU | 32 bit RGBU. |
| FC2_PIXEL_FORMAT_BGR16 | R = G = B = 16 bits. |
| FC2_PIXEL_FORMAT_BGRU16 | 64 bit BGRU. |
| FC2_PIXEL_FORMAT_422YUV8_JPEG | JPEG compressed stream. |
| FC2_NUM_PIXEL_FORMATS | Number of pixel formats. |
| FC2_UNSPECIFIED_PIXEL_FORMAT | Unspecified pixel format. |
| | |

6.22.2.16 fc2PropertyType

enum fc2PropertyType

Camera properties.

Not all properties may be supported, depending on the camera model.

6.22 Enumerations 131

Enumerator

| FC2 BRIGHTNESS | |
|--------------------------------|--|
| FC2_AUTO_EXPOSURE | |
| FC2_SHARPNESS | |
| FC2_WHITE_BALANCE | |
| FC2_HUE | |
| FC2_SATURATION | |
| FC2_GAMMA | |
| FC2_IRIS | |
| FC2_FOCUS | |
| FC2_ZOOM | |
| FC2_PAN | |
| FC2_TILT | |
| FC2_SHUTTER | |
| FC2_GAIN | |
| FC2_TRIGGER_MODE | |
| FC2_TRIGGER_DELAY | |
| FC2_FRAME_RATE | |
| FC2_TEMPERATURE | |
| FC2_UNSPECIFIED_PROPERTY_TYPE | |
| FC2_PROPERTY_TYPE_FORCE_32BITS | |

6.22.2.17 fc2VideoMode

enum fc2VideoMode

DCAM video modes.

| FC2_VIDEOMODE_160x120YUV444 | 160x120 YUV444. |
|------------------------------|---------------------|
| FC2_VIDEOMODE_320x240YUV422 | 320x240 YUV422. |
| FC2_VIDEOMODE_640x480YUV411 | 640x480 YUV411. |
| FC2_VIDEOMODE_640x480YUV422 | 640x480 YUV422. |
| FC2_VIDEOMODE_640x480RGB | 640x480 24-bit RGB. |
| FC2_VIDEOMODE_640x480Y8 | 640x480 8-bit. |
| FC2_VIDEOMODE_640x480Y16 | 640x480 16-bit. |
| FC2_VIDEOMODE_800x600YUV422 | 800x600 YUV422. |
| FC2_VIDEOMODE_800x600RGB | 800x600 RGB. |
| FC2_VIDEOMODE_800x600Y8 | 800x600 8-bit. |
| FC2_VIDEOMODE_800x600Y16 | 800x600 16-bit. |
| FC2_VIDEOMODE_1024x768YUV422 | 1024x768 YUV422. |
| FC2_VIDEOMODE_1024x768RGB | 1024x768 RGB. |
| FC2_VIDEOMODE_1024x768Y8 | 1024x768 8-bit. |
| FC2_VIDEOMODE_1024x768Y16 | 1024x768 16-bit. |
| FC2_VIDEOMODE_1280x960YUV422 | 1280x960 YUV422. |
| FC2_VIDEOMODE_1280x960RGB | 1280x960 RGB. |
| | |

| FC2_VIDEOMODE_1280x960Y8 | 1280x960 8-bit. |
|-------------------------------|--|
| FC2_VIDEOMODE_1280x960Y16 | 1280x960 16-bit. |
| FC2_VIDEOMODE_1600x1200YUV422 | 1600x1200 YUV422. |
| FC2_VIDEOMODE_1600x1200RGB | 1600x1200 RGB. |
| FC2_VIDEOMODE_1600x1200Y8 | 1600x1200 8-bit. |
| FC2_VIDEOMODE_1600x1200Y16 | 1600x1200 16-bit. |
| FC2_VIDEOMODE_FORMAT7 | Custom video mode for Format7 functionality. |
| FC2_NUM_VIDEOMODES | Number of possible video modes. |
| FC2_VIDEOMODE_FORCE_32BITS | |

6.23 GigE specific enumerations

These enumerations are specific to GigE camera operation only.

Enumerations

```
    enum fc2GigEPropertyType {
        FC2_HEARTBEAT,
        FC2_HEARTBEAT_TIMEOUT,
        PACKET_SIZE,
        PACKET_DELAY }
```

Possible properties that can be queried from the camera.

6.23.1 Detailed Description

These enumerations are specific to GigE camera operation only.

6.23.2 Enumeration Type Documentation

6.23.2.1 fc2GigEPropertyType


```
enum fc2GigEPropertyType
```

Possible properties that can be queried from the camera.

| FC2_HEARTBEAT | |
|-----------------------|--|
| FC2_HEARTBEAT_TIMEOUT | |
| PACKET_SIZE | |
| PACKET_DELAY | |

6.24 Structures

Collaboration diagram for Structures:



Modules

• GigE specific structures

These structures are specific to GigE camera operation only.

• IIDC specific structures

These structures are specific to IIDC camera operation only.

· Image saving structures.

These structures define various parameters used for saving images.

· Video saving structures.

These structures define various parameters used for saving videos.

Data Structures

- struct fc2Image
- struct fc2SystemInfo

Description of the system.

struct fc2Version

The current version of the library.

struct fc2IPAddress

IPv4 address.

struct fc2Format7ImageSettings

Format 7 image settings.

· struct fc2Config

Configuration for a camera.

struct fc2TriggerDelayInfo

6.24 Structures 135

Information about a specific camera property.

struct fc2TriggerDelay

A specific camera property.

• struct fc2TriggerModeInfo

Information about a camera trigger property.

• struct fc2TriggerMode

A camera trigger.

· struct fc2StrobeInfo

A camera strobe property.

struct fc2StrobeControl

A camera strobe.

struct fc2TimeStamp

Timestamp information.

struct fc2ConfigROM

Camera configuration ROM.

· struct fc2CameraInfo

Camera information.

• struct fc2EmbeddedImageInfoProperty

Properties of a single embedded image info property.

• struct fc2EmbeddedImageInfo

Properties of the possible embedded image information.

• struct fc2lmageMetadata

Metadata related to an image.

struct fc2LUTData

Information about the camera's look up table.

struct fc2CameraStats

Camera diagnostic information.

• struct fc2PNGOption

Options for saving PNG images.

• struct fc2MJPGOption


Options for saving MJPG files.

6.24.1 Detailed Description

6.25 GigE specific structures

These structures are specific to GigE camera operation only.

Collaboration diagram for GigE specific structures:



Data Structures

struct fc2IPAddress

IPv4 address.

• struct fc2MACAddress

MAC address.

struct fc2GigEProperty

A GigE property.

· struct fc2GigEStreamChannel

Information about a single GigE stream channel.

struct fc2GigEConfig

Configuration for a GigE camera.

• struct fc2GigEImageSettingsInfo

Format 7 information for a single mode.

• struct fc2GigEImageSettings

Image settings for a GigE camera.

6.25.1 Detailed Description

These structures are specific to GigE camera operation only.

6.26 IIDC specific structures

These structures are specific to IIDC camera operation only.

Collaboration diagram for IIDC specific structures:



Data Structures

• struct fc2Format7ImageSettings

Format 7 image settings.

• struct fc2Format7Info

Format 7 information for a single mode.

struct fc2Format7PacketInfo

Format 7 packet information.

6.26.1 Detailed Description

These structures are specific to IIDC camera operation only.

6.27 Image saving structures.

These structures define various parameters used for saving images.

Collaboration diagram for Image saving structures.:



Data Structures

struct fc2PNGOption

Options for saving PNG images.

struct fc2PPMOption

Options for saving PPM images.

• struct fc2PGMOption

Options for saving PGM images.

struct fc2TIFFOption

Options for saving TIFF images.

• struct fc2JPEGOption

Options for saving JPEG image.

struct fc2JPG2Option

Options for saving JPEG2000 image.

struct fc2BMPOption

Options for saving Bitmap image.

struct fc2EventOptions

Options for enabling device event registration.

struct fc2EventCallbackData

Typedefs

- typedef void * fc2CallbackHandle
- typedef void(* fc2BusEventCallback) (void *pParameter, unsigned int serialNumber)
- typedef void(* fc2ImageEventCallback) (fc2Image *image, void *pCallbackData)
- typedef void(* fc2AsyncCommandCallback) (fc2Error retError, void *pUserData)
- typedef void(* fc2CameraEventCallback) (void *pCallbackData)

Enumerations

```
    enum fc2TIFFCompressionMethod {
        FC2_TIFF_NONE = 1,
        FC2_TIFF_PACKBITS,
        FC2_TIFF_DEFLATE,
        FC2_TIFF_ADOBE_DEFLATE,
        FC2_TIFF_CCITTFAX3,
        FC2_TIFF_CCITTFAX4,
        FC2_TIFF_LZW,
```

FC2_TIFF_JPEG }

6.27.1 Detailed Description

These structures define various parameters used for saving images.

6.27.2 Typedef Documentation

6.27.2.1 fc2AsyncCommandCallback

```
typedef void(* fc2AsyncCommandCallback) (fc2Error retError, void *pUserData)
```

6.27.2.2 fc2BusEventCallback

```
typedef void(* fc2BusEventCallback) (void *pParameter, unsigned int serialNumber)
```

6.27.2.3 fc2CallbackHandle

```
typedef void* fc2CallbackHandle
```

6.27.2.4 fc2CameraEventCallback

```
typedef void(* fc2CameraEventCallback) (void *pCallbackData)
```

6.27.2.5 fc2ImageEventCallback

```
{\tt typedef\ void(*\ fc2ImageEventCallback)\ (fc2Image\ *image,\ void\ *pCallbackData)}
```

6.27.3 Enumeration Type Documentation

6.27.3.1 fc2TIFFCompressionMethod

 $\verb"enum fc2TIFFCompressionMethod"$

| FC2_TIFF_NONE | Save without any compression. |
|------------------------|---|
| FC2_TIFF_PACKBITS | Save using PACKBITS compression. |
| FC2_TIFF_DEFLATE | Save using DEFLATE compression (ZLIB compression). |
| FC2_TIFF_ADOBE_DEFLATE | Save using ADOBE DEFLATE compression. |
| FC2_TIFF_CCITTFAX3 | Save using CCITT Group 3 fax encoding. This is only valid for 1-bit images only. Default to LZW for other bit depths. |
| FC2_TIFF_CCITTFAX4 | Save using CCITT Group 4 fax encoding. This is only valid for 1-bit images only. Default to LZW for other bit depths. |
| FC2_TIFF_LZW | Save using LZW compression. |
| FC2_TIFF_JPEG | Save using JPEG compression. This is only valid for 8-bit greyscale and 24-bit only. Default to LZW for other bit depths. |

6.28 Video Recording Operation

The video recording operation provides the functionality for the user to record images to an video file.

Functions

- FLYCAPTURE2_C_API fc2Error fc2VideoCreate (fc2VideoContext *pVideoContext)
 Create a Video context.
- FLYCAPTURE2_C_API fc2Error fc2VideoAVIOpen (fc2VideoContext VideoContext, const char *pFileName, fc2AVIOption *pOption)

Open an AVI file in preparation for writing Images to disk.

• FLYCAPTURE2_C_API fc2Error fc2VideoMJPGOpen (fc2VideoContext VideoContext, const char *pFile → Name, fc2MJPGOption *pOption)

Open an MJPEG file in preparation for writing Images to disk.

• FLYCAPTURE2_C_API fc2Error fc2VideoH264Open (fc2VideoContext VideoContext, const char *pFile
Name, fc2H264Option *pOption)

Open an H.264 video file in preparation for writing Images to disk.

- FLYCAPTURE2_C_API fc2Error fc2VideoAppend (fc2VideoContext VideoContext, fc2Image *pImage)
 Append an image to the video file.
- FLYCAPTURE2_C_API fc2Error fc2VideoSetMaximumSize (fc2VideoContext VideoContext, unsigned int size)

Set the maximum file size (in megabytes) of a AVI/MP4 file.

- FLYCAPTURE2_C_API fc2Error fc2VideoClose (fc2VideoContext VideoContext)
 Close the video file.
- FLYCAPTURE2_C_API fc2Error fc2VideoDestroy (fc2VideoContext VideoContext)

Destroy a video context.

6.28.1 Detailed Description

The video recording operation provides the functionality for the user to record images to an video file.

6.28.2 Function Documentation

6.28.2.1 fc2VideoAppend()

Append an image to the video file.

Parameters

| VideoContext | The video context to use. |
|--------------|---------------------------|
| plmage | The image to append. |

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.2 fc2VideoAVIOpen()

Open an AVI file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

Parameters

| VideoContext | The video context to use. |
|--------------|-----------------------------------|
| pFileName | The filename of the AVI file. |
| pOption | Options to apply to the AVI file. |

See also

```
SetMaximumFileSize() fc2Close() fc2AVIOption
```

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.3 fc2VideoClose()

Close the video file.

Parameters

| VideoContext | The video context to use. |
|--------------|---------------------------|

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.4 fc2VideoCreate()

Create a Video context.

Parameters

```
pVideoContext | A video context.
```

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.5 fc2VideoDestroy()

Destroy a video context.

Parameters

| VideoContext | A video context. |
|--------------|------------------|
| | |

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.6 fc2VideoH264Open()

Open an H.264 video file in preparation for writing Images to disk.

If the file extension is not specified, MP4 will be used as the default container. Consult ffmpeg documentation for a list of supported containers.

Parameters

| pFileName | The filename of the video file. |
|-----------|---|
| pOption | H.264 options to apply to the video file. |

See also

```
fc2Close()
fc2H264Option
```

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.7 fc2VideoMJPGOpen()

Open an MJPEG file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

Parameters

| VideoContext | The AVI context to use. |
|--------------|-----------------------------------|
| pFileName | The filename of the AVI file. |
| pOption | Options to apply to the AVI file. |

See also

```
fc2Close()
fc2MJPGOption
```

Returns

A fc2Error indicating the success or failure of the function.

6.28.2.8 fc2VideoSetMaximumSize()

Set the maximum file size (in megabytes) of a AVI/MP4 file.

A new AVI/MP4 file is created automatically when file size limit is reached. Setting a maximum size of 0 indicates no limit on file size.

Parameters

| VideoContext | The video context to use. |
|--------------|------------------------------------|
| size | The maximum video file size in MB. |

Returns

A fc2Error indicating the success or failure of the function.

6.29 Video saving structures.

These structures define various parameters used for saving videos.

Collaboration diagram for Video saving structures.:



Data Structures

• struct fc2MJPGOption

Options for saving MJPG files.

• struct fc2H264Option

Options for saving H264 files.

• struct fc2AVIOption

Options for saving AVI files.

6.29.1 Detailed Description

These structures define various parameters used for saving videos.

Chapter 7

Data Structure Documentation

7.1 fc2AVIOption Struct Reference

Options for saving AVI files.

Data Fields

float frameRate

Frame rate of the stream.

• unsigned int reserved [256]

Reserved for future use.

7.1.1 Detailed Description

Options for saving AVI files.

7.1.2 Field Documentation

7.1.2.1 frameRate

float frameRate

Frame rate of the stream.

7.1.2.2 reserved

```
unsigned int reserved[256]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2VideoDefs_C.h

7.2 fc2BMPOption Struct Reference

Options for saving Bitmap image.

Data Fields

- BOOL indexedColor_8bit
- unsigned int reserved [16]

Reserved for future use.

7.2.1 Detailed Description

Options for saving Bitmap image.

7.2.2 Field Documentation

7.2.2.1 indexedColor_8bit

```
BOOL indexedColor_8bit
```

7.2.2.2 reserved

```
unsigned int reserved[16]
```

Reserved for future use.


The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.3 fc2CameraInfo Struct Reference

Camera information.

Collaboration diagram for fc2CameraInfo:



Data Fields

• unsigned int serialNumber

Device serial number.

fc2InterfaceType interfaceType

Interface type.

• fc2DriverType driverType

Driver type.

• BOOL isColorCamera

Flag indicating if this is a color camera.

char modelName [MAX_STRING_LENGTH]

Device model name.

• char vendorName [MAX_STRING_LENGTH]

Device vendor name.

char sensorInfo [MAX_STRING_LENGTH]

String detailing the sensor information.

char sensorResolution [MAX_STRING_LENGTH]

String providing the sensor resolution.

• char driverName [MAX_STRING_LENGTH]

Driver name of driver being used.

char firmwareVersion [MAX_STRING_LENGTH]

Firmware version of camera.

• char firmwareBuildTime [MAX_STRING_LENGTH]

Firmware build time.

fc2BusSpeed maximumBusSpeed

Maximum bus speed.

fc2BayerTileFormat bayerTileFormat

Bayer tile format.

fc2PCleBusSpeed pcieBusSpeed

Bus number, set to 0 for GigE and USB cameras.

• unsigned short nodeNumber

ieee1394 Node number, set to 0 for GigE and USB cameras

unsigned short busNumber

PCIe Bus Speed, set to PCIE_BUSSPEED_UNKNOWN for unsupported drivers.

• unsigned int reserved [16]

Reserved for future use.

IIDC specific information

· unsigned int iidcVer

DCAM version.

fc2ConfigROM configROM

Configuration ROM data.

GigE specific information

• unsigned int gigEMajorVersion

GigE Vision version.

• unsigned int gigEMinorVersion

GigE Vision minor version.

• char userDefinedName [MAX_STRING_LENGTH]

User defined name.

char xmlURL1 [MAX_STRING_LENGTH]

XML URL 1.

char xmlURL2 [MAX_STRING_LENGTH]

XML URL 2.

• fc2MACAddress macAddress

MAC address.

fc2IPAddress ipAddress

IP address.

fc2IPAddress subnetMask

Subnet mask.

· fc2IPAddress defaultGateway

Default gateway.

• unsigned int ccpStatus

Status/Content of CCP register.

· unsigned int applicationIPAddress

Local Application IP Address.

unsigned int applicationPort

Local Application port.

7.3.1 Detailed Description

Camera information.

7.3.2 Field Documentation

7.3.2.1 applicationIPAddress

 ${\tt unsigned\ int\ application IPAddress}$

Local Application IP Address.

7.3.2.2 applicationPort

unsigned int applicationPort

Local Application port.

7.3.2.3 bayerTileFormat

fc2BayerTileFormat bayerTileFormat

Bayer tile format.

7.3.2.4 busNumber

unsigned short busNumber

PCIe Bus Speed, set to PCIE_BUSSPEED_UNKNOWN for unsupported drivers.

7.3.2.5 ccpStatus

unsigned int ccpStatus

Status/Content of CCP register.

7.3.2.6 configROM

fc2ConfigROM configROM

Configuration ROM data.

7.3.2.7 defaultGateway fc2IPAddress defaultGateway Default gateway. 7.3.2.8 driverName char driverName[MAX_STRING_LENGTH] Driver name of driver being used. 7.3.2.9 driverType fc2DriverType driverType Driver type. 7.3.2.10 firmwareBuildTime char firmwareBuildTime[MAX_STRING_LENGTH] Firmware build time. 7.3.2.11 firmwareVersion

char firmwareVersion[MAX_STRING_LENGTH]

Firmware version of camera.

7.3.2.12 gigEMajorVersion

unsigned int gigEMajorVersion

GigE Vision version.

7.3.2.13 gigEMinorVersion ${\tt unsigned\ int\ gigEMinorVersion}$ GigE Vision minor version. 7.3.2.14 iidcVer unsigned int iidcVer DCAM version. 7.3.2.15 interfaceType fc2InterfaceType interfaceType Interface type. 7.3.2.16 ipAddress fc2IPAddress ipAddress IP address. 7.3.2.17 isColorCamera BOOL isColorCamera Flag indicating if this is a color camera. 7.3.2.18 macAddress fc2MACAddress macAddress MAC address.

7.3.2.19 maximumBusSpeed

fc2BusSpeed maximumBusSpeed

Maximum bus speed.

7.3.2.20 modelName

char modelName[MAX_STRING_LENGTH]

Device model name.

7.3.2.21 nodeNumber

unsigned short nodeNumber

ieee1394 Node number, set to 0 for GigE and USB cameras

7.3.2.22 pcieBusSpeed

fc2PCIeBusSpeed pcieBusSpeed

Bus number, set to 0 for GigE and USB cameras.

7.3.2.23 reserved

unsigned int reserved[16]

Reserved for future use.

7.3.2.24 sensorInfo

char sensorInfo[MAX_STRING_LENGTH]

String detailing the sensor information.

7.3.2.25 sensorResolution char sensorResolution[MAX_STRING_LENGTH] String providing the sensor resolution. 7.3.2.26 serialNumber unsigned int serialNumber Device serial number. 7.3.2.27 subnetMask fc2IPAddress subnetMask Subnet mask. 7.3.2.28 userDefinedName char userDefinedName[MAX_STRING_LENGTH] User defined name. 7.3.2.29 vendorName char vendorName[MAX_STRING_LENGTH] Device vendor name. 7.3.2.30 xmlURL1 char xmlURL1[MAX_STRING_LENGTH]

XML URL 1.

7.3.2.31 xmlURL2

char xmlURL2[MAX_STRING_LENGTH]

XML URL 2.


The documentation for this struct was generated from the following file:

FlyCapture2Defs_C.h

7.4 fc2CameraStats Struct Reference

Camera diagnostic information.

Collaboration diagram for fc2CameraStats:



Data Fields

- · unsigned int imageDropped
- · unsigned int imageCorrupt
- unsigned int imageXmitFailed
- unsigned int imageDriverDropped
- · unsigned int regReadFailed
- unsigned int regWriteFailed
- unsigned int portErrors
- BOOL cameraPowerUp
- float cameraVoltages [8]unsigned int numVoltages

The number of voltage registers available.

- float cameraCurrents [8]
- unsigned int numCurrents

The number of current registers available.

- unsigned int temperature
- unsigned int timeSinceInitialization
- unsigned int timeSinceBusReset
- fc2TimeStamp timeStamp
- unsigned int numResendPacketsRequested
- unsigned int numResendPacketsReceived
- unsigned int reserved [16]

Reserved for future use.

7.4.1 Detailed Description

Camera diagnostic information.

7.4.2 Field Documentation

7.4.2.1 cameraCurrents

float cameraCurrents[8]

7.4.2.2 cameraPowerUp

BOOL cameraPowerUp

7.4.2.3 cameraVoltages

float cameraVoltages[8]

7.4.2.4 imageCorrupt

unsigned int imageCorrupt

7.4.2.5 imageDriverDropped

 ${\tt unsigned\ int\ imageDriverDropped}$

7.4.2.6 imageDropped

unsigned int imageDropped

7.4.2.7 imageXmitFailed

unsigned int imageXmitFailed

7.4.2.8 numCurrents

unsigned int numCurrents

The number of current registers available.

0: the values in cameraCurrents[] are invalid.

7.4.2.9 numResendPacketsReceived

unsigned int numResendPacketsReceived

7.4.2.10 numResendPacketsRequested

unsigned int numResendPacketsRequested

7.4.2.11 numVoltages

unsigned int numVoltages

The number of voltage registers available.

0: the values in cameraVoltages[] are invalid.

7.4.2.12 portErrors

 ${\tt unsigned\ int\ portErrors}$

7.4.2.13 regReadFailed

unsigned int regReadFailed

7.4.2.14 regWriteFailed

unsigned int regWriteFailed

7.4.2.15 reserved

unsigned int reserved[16]

Reserved for future use.

7.4.2.16 temperature

unsigned int temperature

7.4.2.17 timeSinceBusReset

unsigned int timeSinceBusReset

7.4.2.18 timeSinceInitialization

 ${\tt unsigned\ int\ timeSinceInitialization}$

7.4.2.19 timeStamp

fc2TimeStamp timeStamp

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.5 fc2Config Struct Reference

Configuration for a camera.

Data Fields

• unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

unsigned int numImageNotifications

Number of notifications per image.

· unsigned int minNumImageNotifications

Minimum number of notifications needed for the current image settings on the camera.

· int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

• fc2GrabMode grabMode

Grab mode for the camera.

· BOOL highPerformanceRetrieveBuffer

This parameter enables RetrieveBuffer to run in high performance mode.

• fc2BusSpeed isochBusSpeed

Isochronous bus speed.

• fc2BusSpeed asyncBusSpeed

Asynchronous bus speed.

• fc2BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

· unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

• unsigned int registerTimeout

Register read/write timeout value, in microseconds.

• unsigned int reserved [16]

Reserved for future use.

7.5.1 Detailed Description

Configuration for a camera.

These options are options that are generally should be set before starting isochronous transfer.

7.5.2 Field Documentation

7.5.2.1 asyncBusSpeed

fc2BusSpeed asyncBusSpeed

Asynchronous bus speed.

7.5.2.2 bandwidthAllocation

fc2BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

7.5.2.3 grabMode

fc2GrabMode grabMode

Grab mode for the camera.

The default is DROP FRAMES.

7.5.2.4 grabTimeout

int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

7.5.2.5 highPerformanceRetrieveBuffer

BOOL highPerformanceRetrieveBuffer

This parameter enables RetrieveBuffer to run in high performance mode.

This means that any interaction with the camera, other than grabbing the image is disabled. Currently Retrieve buffer reads registers on the camera to determine which embedded image information settings have been enabled, and it reads what the bayer tile is currently set to. When High Performance mode is on, these reads are disabled. This means that any changes to the Bayer Tile or to the Embedded image info after StartCapture() will not be tracked when made using direct register writes. If the corresponding SetEmbededImageInfo() and GetEmbededImageInfo() calls are used then the changes will be appropriately reflected. This also means that changes to embedded image info from other processes will not be updated either.

7.5.2.6 isochBusSpeed

fc2BusSpeed isochBusSpeed

Isochronous bus speed.

7.5.2.7 minNumImageNotifications

unsigned int minNumImageNotifications

Minimum number of notifications needed for the current image settings on the camera.

Read-only value.

7.5.2.8 numBuffers

unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

7.5.2.9 numlmageNotifications

unsigned int numImageNotifications

Number of notifications per image.

This value should only be set after the image settings to be used is set to the camera. The default number of notifications is 1.

There are 4 general scenarios:

- 1 notification End of image
- 2 notifications After first packet and end of image
- · 3 notifications After first packet, middle of image, end of image
- x notifications After first packet, (x -2) spread evenly, end of image

Specifying zero for the number of notifications will be ignored (the current value will not be modified).

Note that the event numbers start at 0. Ex. when 3 notifications are used, the three events will be 0, 1 and 2.

7.5.2.10 registerTimeout

unsigned int registerTimeout

Register read/write timeout value, in microseconds.

The default value is dependent on the interface type.

7.5.2.11 registerTimeoutRetries

```
unsigned int registerTimeoutRetries
```

Number of retries to perform when a register read/write timeout is received by the library.

The default value is 0.

7.5.2.12 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.6 fc2ConfigROM Struct Reference

Camera configuration ROM.

Data Fields

· unsigned int nodeVendorld

Vendor ID of a node.

· unsigned int chipIdHi

Chip ID (high part).

· unsigned int chipIdLo

Chip ID (low part).

unsigned int unitSpecId

Unit Spec ID, usually 0xa02d.

• unsigned int unitSWVer

Unit software version.

• unsigned int unitSubSWVer

Unit sub software version.

unsigned int vendorUniqueInfo_0

Vendor unique info 0.

• unsigned int vendorUniqueInfo_1

Vendor unique info 1.

unsigned int vendorUniqueInfo_2

Vendor unique info 2.

• unsigned int vendorUniqueInfo_3

Vendor unique info 3.

char pszKeyword [MAX_STRING_LENGTH]

Keyword.

• unsigned int reserved [16]

Reserved for future use.

7.6.1 Detailed Description

Camera configuration ROM.

7.6.2 Field Documentation

7.6.2.1 chipldHi

unsigned int chipIdHi

Chip ID (high part).

7.6.2.2 chipldLo

unsigned int chipIdLo

Chip ID (low part).

7.6.2.3 nodeVendorld

unsigned int nodeVendorId

Vendor ID of a node.

7.6.2.4 pszKeyword

char pszKeyword[MAX_STRING_LENGTH]

Keyword.

7.6.2.5 reserved

unsigned int reserved[16]

Reserved for future use.

7.6.2.6 unitSpecId ${\tt unsigned\ int\ unitSpecId}$ Unit Spec ID, usually 0xa02d. 7.6.2.7 unitSubSWVer unsigned int unitSubSWVer Unit sub software version. 7.6.2.8 unitSWVer unsigned int unitSWVer Unit software version. 7.6.2.9 vendorUniqueInfo_0 unsigned int vendorUniqueInfo_0 Vendor unique info 0. 7.6.2.10 vendorUniqueInfo_1 unsigned int vendorUniqueInfo_1 Vendor unique info 1. 7.6.2.11 vendorUniqueInfo_2 unsigned int vendorUniqueInfo_2

Vendor unique info 2.

7.6.2.12 vendorUniqueInfo_3

unsigned int vendorUniqueInfo_3

Vendor unique info 3.


The documentation for this struct was generated from the following file:

• FlyCapture2Defs C.h

7.7 fc2EmbeddedImageInfo Struct Reference

Properties of the possible embedded image information.

Collaboration diagram for fc2EmbeddedImageInfo:



Data Fields

- fc2EmbeddedImageInfoProperty timestamp
- fc2EmbeddedImageInfoProperty gain
- · fc2EmbeddedImageInfoProperty shutter
- fc2EmbeddedImageInfoProperty brightness
- · fc2EmbeddedImageInfoProperty exposure
- fc2EmbeddedImageInfoProperty whiteBalance
- · fc2EmbeddedImageInfoProperty frameCounter
- fc2EmbeddedImageInfoProperty strobePattern
- fc2EmbeddedImageInfoProperty GPIOPinState
- fc2EmbeddedImageInfoProperty ROIPosition

7.7.1 Detailed Description

Properties of the possible embedded image information.

7.7.2 Field Documentation

7.7.2.1 brightness

 ${\tt fc2EmbeddedImageInfoProperty\ brightness}$

7.7.2.2 exposure

fc2EmbeddedImageInfoProperty exposure

7.7.2.3 frameCounter

fc2EmbeddedImageInfoProperty frameCounter

7.7.2.4 gain

 ${\tt fc2EmbeddedImageInfoProperty\ gain}$

7.7.2.5 GPIOPinState

 ${\tt fc2EmbeddedImageInfoProperty\ GPIOPinState}$

7.7.2.6 ROIPosition

fc2EmbeddedImageInfoProperty ROIPosition

7.7.2.7 shutter

fc2EmbeddedImageInfoProperty shutter

7.7.2.8 strobePattern

fc2EmbeddedImageInfoProperty strobePattern

7.7.2.9 timestamp

 ${\tt fc2EmbeddedImageInfoProperty\ timestamp}$

7.7.2.10 whiteBalance

 ${\tt fc2EmbeddedImageInfoProperty\ whiteBalance}$

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.8 fc2EmbeddedImageInfoProperty Struct Reference

Properties of a single embedded image info property.

Data Fields

· BOOL available

Whether this property is available.

BOOL onOff

Whether this property is on or off.

7.8.1 Detailed Description

Properties of a single embedded image info property.

7.8.2 Field Documentation

7.8.2.1 available

BOOL available

Whether this property is available.

7.8.2.2 onOff

BOOL onOff

Whether this property is on or off.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.9 fc2EventCallbackData Struct Reference

Data Fields

void * EventUserData

Pointer to the user-supplied data struct.

size_t EventUserDataSize

Size of the user data supplied to the RegisterEvent() function.

const char * EventName

The event name used to register the event.

• unsigned long long EventID

The device register which EventName maps to.

unsigned long long EventTimestamp

Timestamp indicated the time (as reported by the camera) at which the camera exposure operation completed.

void * EventData

A pointer to additional data pertaining to the event which just trigger the callback function.

• size_t EventDataSize

The size of the structure pointed to by EventData.

7.9.1 Field Documentation

7.9.1.1 EventData

void* EventData

A pointer to additional data pertaining to the event which just trigger the callback function.

The data may be of difference sizes or may not even be allocated, depending on the type of event which triggered the callback.

7.9.1.2 EventDataSize

size_t EventDataSize

The size of the structure pointed to by EventData.

This value should be checked, especially if there are events which can trigger variable-length event data to be returned to the user when the callback function is issued.

7.9.1.3 EventID

unsigned long long EventID

The device register which EventName maps to.

Provides an alternate means of indexing into different event types.

7.9.1.4 EventName

const char* EventName

The event name used to register the event.

Provided so the user knows which event triggered the callback.

7.9.1.5 EventTimestamp

unsigned long long EventTimestamp

Timestamp indicated the time (as reported by the camera) at which the camera exposure operation completed.

This can be compared with image timestamps if there is a need to map event timestamps to specific images, if applicable.

7.9.1.6 EventUserData

void* EventUserData

Pointer to the user-supplied data struct.

7.9.1.7 EventUserDataSize

size_t EventUserDataSize

Size of the user data supplied to the RegisterEvent() function.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.10 fc2EventOptions Struct Reference

Options for enabling device event registration.

Data Fields

• fc2CameraEventCallback EventCallbackFcn

Callback function pointer.

• const char * EventName

Event name to register.

const void * EventUserData

Pointer to callback data to be passed to the callback function.

• size_t EventUserDataSize

Size of the underlying struct passed as eventCallbackData for sanity checks.

7.10.1 Detailed Description

Options for enabling device event registration.

7.10.2 Field Documentation

7.10.2.1 EventCallbackFcn

fc2CameraEventCallback EventCallbackFcn

Callback function pointer.

7.10.2.2 EventName

const char* EventName

Event name to register.

7.10.2.3 EventUserData

const void* EventUserData

Pointer to callback data to be passed to the callback function.

7.10.2.4 EventUserDataSize

size_t EventUserDataSize

Size of the underlying struct passed as eventCallbackData for sanity checks.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.11 fc2Format7ImageSettings Struct Reference

Format 7 image settings.

Data Fields

• fc2Mode mode

Format 7 mode.

unsigned int offsetX

Horizontal image offset.

· unsigned int offsetY

Vertical image offset.

· unsigned int width

Width of image.

· unsigned int height

Height of image.

fc2PixelFormat pixelFormat

Pixel format of image.

• unsigned int reserved [8]

Reserved for future use.

7.11.1 Detailed Description

Format 7 image settings.

7.11.2 Field Documentation

7.11.2.1 height

unsigned int height

Height of image.

7.11.2.2 mode fc2Mode mode Format 7 mode. 7.11.2.3 offsetX unsigned int offsetX Horizontal image offset. 7.11.2.4 offsetY unsigned int offsetY Vertical image offset. 7.11.2.5 pixelFormat fc2PixelFormat pixelFormat Pixel format of image. 7.11.2.6 reserved unsigned int reserved[8] Reserved for future use. 7.11.2.7 width unsigned int width Width of image.

• FlyCapture2Defs_C.h

The documentation for this struct was generated from the following file:

7.12 fc2Format7Info Struct Reference

Format 7 information for a single mode.

Data Fields

· fc2Mode mode

Format 7 mode.

· unsigned int maxWidth

Maximum image width.

unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

unsigned int offsetVStepSize

Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

• unsigned int imageVStepSize

Vertical step size for the image.

unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

• unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

• unsigned int packetSize

Current packet size in bytes.

• unsigned int minPacketSize

Minimum packet size in bytes for current mode.

• unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

float percentage

Current packet size as a percentage of maximum packet size.

• unsigned int reserved [16]

Reserved for future use.

7.12.1 Detailed Description

Format 7 information for a single mode.

7.12.2 Field Documentation

7.12.2.1 imageHStepSize

unsigned int imageHStepSize

Horizontal step size for the image.

7.12.2.2 imageVStepSize

unsigned int imageVStepSize

Vertical step size for the image.

7.12.2.3 maxHeight

unsigned int maxHeight

Maximum image height.

7.12.2.4 maxPacketSize

unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

7.12.2.5 maxWidth

unsigned int maxWidth

Maximum image width.

7.12.2.6 minPacketSize

unsigned int minPacketSize

Minimum packet size in bytes for current mode.

7.12.2.7 mode

fc2Mode mode

Format 7 mode.

7.12.2.8 offsetHStepSize

unsigned int offsetHStepSize

Horizontal step size for the offset.

7.12.2.9 offsetVStepSize

unsigned int offsetVStepSize

Vertical step size for the offset.

7.12.2.10 packetSize

unsigned int packetSize

Current packet size in bytes.

7.12.2.11 percentage

float percentage

Current packet size as a percentage of maximum packet size.

7.12.2.12 pixelFormatBitField

unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

7.12.2.13 reserved

unsigned int reserved[16]

Reserved for future use.

7.12.2.14 vendorPixelFormatBitField

 ${\tt unsigned\ int\ vendorPixelFormatBitField}$

Vendor unique pixel formats in a bit field.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.13 fc2Format7PacketInfo Struct Reference

Format 7 packet information.

Data Fields

- · unsigned int recommendedBytesPerPacket
 - Recommended bytes per packet.
- unsigned int maxBytesPerPacket
 - Maximum bytes per packet.
- unsigned int unitBytesPerPacket
 - Minimum bytes per packet.
- unsigned int reserved [8]

Reserved for future use.

7.13.1 Detailed Description

Format 7 packet information.

7.13.2 Field Documentation

7.13.2.1 maxBytesPerPacket

unsigned int maxBytesPerPacket

Maximum bytes per packet.

7.13.2.2 recommendedBytesPerPacket

 ${\tt unsigned\ int\ recommended BytesPerPacket}$

Recommended bytes per packet.

7.13.2.3 reserved

unsigned int reserved[8]

Reserved for future use.

7.13.2.4 unitBytesPerPacket

unsigned int unitBytesPerPacket

Minimum bytes per packet.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.14 fc2GigEConfig Struct Reference

Configuration for a GigE camera.

Data Fields

• BOOL enablePacketResend

Turn on/off packet resend functionality.

unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

• unsigned int registerTimeout

Register read/write timeout value, in microseconds.

• unsigned int reserved [8]

7.14.1 Detailed Description

Configuration for a GigE camera.

These options are options that are generally should be set before starting isochronous transfer.

7.14.2 Field Documentation

7.14.2.1 enablePacketResend

BOOL enablePacketResend

Turn on/off packet resend functionality.

7.14.2.2 registerTimeout

```
unsigned int registerTimeout
```

Register read/write timeout value, in microseconds.

The default value is dependent on the interface type.

7.14.2.3 registerTimeoutRetries

```
unsigned int registerTimeoutRetries
```

Number of retries to perform when a register read/write timeout is received by the library.

The default value is 0.

7.14.2.4 reserved

```
unsigned int reserved[8]
```

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.15 fc2GigElmageSettings Struct Reference

Image settings for a GigE camera.

Data Fields

- unsigned int offsetX
 - Horizontal image offset.
- · unsigned int offsetY
 - Vertical image offset.
- unsigned int width
 - Width of image.
- unsigned int height
 - Height of image.
- fc2PixelFormat pixelFormat
 - Pixel format of image.
- unsigned int reserved [8]
 - Reserved for future use.

7.15.1 Detailed Description

Image settings for a GigE camera.

7.15.2 Field Documentation

7.15.2.1 height

unsigned int height

Height of image.

7.15.2.2 offsetX

unsigned int offsetX

Horizontal image offset.

7.15.2.3 offsetY

unsigned int offsetY

Vertical image offset.

7.15.2.4 pixelFormat

fc2PixelFormat pixelFormat

Pixel format of image.

7.15.2.5 reserved

unsigned int reserved[8]

Reserved for future use.

7.15.2.6 width

unsigned int width

Width of image.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.16 fc2GigElmageSettingsInfo Struct Reference

Format 7 information for a single mode.

Data Fields

- unsigned int maxWidth
 - Maximum image width.
- · unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

• unsigned int offsetVStepSize

Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

• unsigned int imageVStepSize

Vertical step size for the image.

· unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

· unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

• unsigned int reserved [16]

Reserved for future use.

7.16.1 Detailed Description

Format 7 information for a single mode.

7.16.2 Field Documentation

7.16.2.1 imageHStepSize

unsigned int imageHStepSize

Horizontal step size for the image.

7.16.2.2 imageVStepSize

unsigned int imageVStepSize

Vertical step size for the image.

7.16.2.3 maxHeight

unsigned int maxHeight

Maximum image height.

7.16.2.4 maxWidth

unsigned int maxWidth

Maximum image width.

7.16.2.5 offsetHStepSize

unsigned int offsetHStepSize

Horizontal step size for the offset.

7.16.2.6 offsetVStepSize

unsigned int offsetVStepSize

Vertical step size for the offset.

7.16.2.7 pixelFormatBitField

unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

7.16.2.8 reserved

unsigned int reserved[16]

Reserved for future use.

7.16.2.9 vendorPixelFormatBitField

unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.17 fc2GigEProperty Struct Reference

A GigE property.

Data Fields

• fc2GigEPropertyType propType

The type of property.

BOOL isReadable

Whether the property is readable.

· BOOL isWritable

Whether the property is writable.

unsigned int min

Minimum value.

unsigned int max

Maximum value.

· unsigned int value

Current value.

• unsigned int reserved [8]

7.17.1 Detailed Description

A GigE property.

7.17.2 Field Documentation

7.17.2.1 isReadable

BOOL isReadable

Whether the property is readable.

If this is false, then no other value in this structure is valid.

7.17.2.2 isWritable

BOOL isWritable

Whether the property is writable.

7.17.2.3 max

unsigned int max

Maximum value.

7.17.2.4 min

unsigned int min

Minimum value.

7.17.2.5 propType

fc2GigEPropertyType propType

The type of property.

7.17.2.6 reserved

unsigned int reserved[8]

7.17.2.7 value

unsigned int value

Current value.


The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.18 fc2GigEStreamChannel Struct Reference

Information about a single GigE stream channel.

Collaboration diagram for fc2GigEStreamChannel:



Data Fields

unsigned int networkInterfaceIndex

Network interface index used (or to use).

unsigned int hostPort

Host port on the PC where the camera will send the data stream.

BOOL doNotFragment

Disable IP fragmentation of packets.

· unsigned int packetSize

Packet size, in bytes.

• unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

• fc2IPAddress destinationIpAddress

Destination IP address.

• unsigned int sourcePort

Source UDP port of the stream channel.

• unsigned int reserved [8]

7.18.1 Detailed Description

Information about a single GigE stream channel.

7.18.2 Field Documentation

7.18.2.1 destinationIpAddress

fc2IPAddress destinationIpAddress

Destination IP address.

It can be a multicast or unicast address.

7.18.2.2 doNotFragment

BOOL doNotFragment

Disable IP fragmentation of packets.

7.18.2.3 hostPort

unsigned int hostPort

Host port on the PC where the camera will send the data stream.

7.18.2.4 interPacketDelay

unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

7.18.2.5 networkInterfaceIndex

unsigned int networkInterfaceIndex

Network interface index used (or to use).

7.18.2.6 packetSize

unsigned int packetSize

Packet size, in bytes.

7.18.2.7 reserved

unsigned int reserved[8]

7.18.2.8 sourcePort

unsigned int sourcePort

Source UDP port of the stream channel.

Read only.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.19 fc2H264Option Struct Reference

Options for saving H264 files.

Data Fields

· float frameRate

Frame rate of the stream.

· unsigned int width

Width of source image.

· unsigned int height

Height of source image.

· unsigned int bitrate

Bitrate to encode at.

· unsigned int reserved [256]

Reserved for future use.

7.19.1 Detailed Description

Options for saving H264 files.

7.19.2 Field Documentation

7.19.2.1 bitrate unsigned int bitrate Bitrate to encode at. 7.19.2.2 frameRate float frameRate Frame rate of the stream. 7.19.2.3 height unsigned int height Height of source image. 7.19.2.4 reserved unsigned int reserved[256] Reserved for future use. 7.19.2.5 width unsigned int width Width of source image.

• FlyCapture2VideoDefs_C.h

The documentation for this struct was generated from the following file:

7.20 fc2Image Struct Reference

Data Fields

- unsigned int rows
- unsigned int cols
- · unsigned int stride
- unsigned char * pData
- unsigned int dataSize
- unsigned int receivedDataSize
- fc2PixelFormat format
- fc2BayerTileFormat bayerFormat
- fc2lmagelmpl imagelmpl

7.20.1 Field Documentation

7.20.1.1 bayerFormat

fc2BayerTileFormat bayerFormat

7.20.1.2 cols

unsigned int cols

7.20.1.3 dataSize

unsigned int dataSize

7.20.1.4 format

fc2PixelFormat format

7.20.1.5 imageImpl

fc2ImageImpl imageImpl

7.20.1.6 pData

unsigned char* pData

7.20.1.7 receivedDataSize

unsigned int receivedDataSize

7.20.1.8 rows

unsigned int rows

7.20.1.9 stride

unsigned int stride

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.21 fc2ImageMetadata Struct Reference

Metadata related to an image.

Data Fields

unsigned int embeddedTimeStamp

Embedded timestamp.

• unsigned int embeddedGain

Embedded gain.

· unsigned int embeddedShutter

Embedded shutter.

• unsigned int embeddedBrightness

Embedded brightness.

• unsigned int embeddedExposure

Embedded exposure.

• unsigned int embeddedWhiteBalance

Embedded white balance.

· unsigned int embeddedFrameCounter

Embedded frame counter.

• unsigned int embeddedStrobePattern

Embedded strobe pattern.

• unsigned int embeddedGPIOPinState

Embedded GPIO pin state.

• unsigned int embeddedROIPosition

Embedded ROI position.

· unsigned int reserved [31]

Reserved for future use.

7.21.1 Detailed Description

Metadata related to an image.

7.21.2 Field Documentation

7.21.2.1 embeddedBrightness

unsigned int embeddedBrightness

Embedded brightness.

7.21.2.2 embeddedExposure

unsigned int embeddedExposure

Embedded exposure.

7.21.2.3 embeddedFrameCounter

unsigned int embeddedFrameCounter

Embedded frame counter.

7.21.2.4 embeddedGain

unsigned int embeddedGain

Embedded gain.

7.21.2.5 embeddedGPIOPinState

unsigned int embeddedGPIOPinState

Embedded GPIO pin state.

7.21.2.6 embeddedROIPosition

unsigned int embeddedROIPosition

Embedded ROI position.

7.21.2.7 embeddedShutter

unsigned int embeddedShutter

Embedded shutter.

7.21.2.8 embeddedStrobePattern

 ${\tt unsigned\ int\ embeddedStrobePattern}$

Embedded strobe pattern.

7.21.2.9 embeddedTimeStamp

unsigned int embeddedTimeStamp

Embedded timestamp.

7.21.2.10 embeddedWhiteBalance

 ${\tt unsigned\ int\ embeddedWhiteBalance}$

Embedded white balance.

7.21.2.11 reserved

unsigned int reserved[31]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.22 fc2InternalContext Struct Reference

Data Fields

- FlyCapture2::BusManager * pBusMgrFlyCapture2::CameraBase * pCamera
- 7.22.1 Field Documentation

7.22.1.1 pBusMgr

FlyCapture2::BusManager* pBusMgr

7.22.1.2 pCamera

FlyCapture2::CameraBase* pCamera

The documentation for this struct was generated from the following file:

• FlyCapture2Internal_C.h

7.23 fc2InternalGuiContext Struct Reference

Data Fields

- FlyCapture2::CameraSelectionDlg * pCameraSelectionDlg
- FlyCapture2::CameraControlDlg * pCameraControlDlg

7.23.1 Field Documentation

7.23.1.1 pCameraControlDlg

FlyCapture2::CameraControlDlg* pCameraControlDlg

7.23.1.2 pCameraSelectionDlg


FlyCapture2::CameraSelectionDlg* pCameraSelectionDlg

The documentation for this struct was generated from the following file:

• FlyCapture2Internal_C.h

7.24 fc2InternalImageCallback Struct Reference

Collaboration diagram for fc2InternalImageCallback:



Data Fields

- fc2ImageEventCallback pCallback
- void * pCallbackData

7.24.1 Field Documentation

7.24.1.1 pCallback

fc2ImageEventCallback pCallback

7.24.1.2 pCallbackData

void* pCallbackData

The documentation for this struct was generated from the following file:

• FlyCapture2Internal_C.h

7.25 fc2IPAddress Struct Reference

IPv4 address.

Data Fields

• unsigned char octets [4]

7.25.1 Detailed Description

IPv4 address.

7.25.2 Field Documentation

7.25.2.1 octets

unsigned char octets[4]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.26 fc2JPEGOption Struct Reference

Options for saving JPEG image.

Data Fields

• BOOL progressive

Whether to save as a progressive JPEG file.

· unsigned int quality

JPEG image quality in range (0-100).

• unsigned int reserved [16]

Reserved for future use.

7.26.1 Detailed Description

Options for saving JPEG image.

7.26.2 Field Documentation

7.26.2.1 progressive

```
BOOL progressive
```

Whether to save as a progressive JPEG file.

7.26.2.2 quality

```
unsigned int quality
```

JPEG image quality in range (0-100).

- 100 Superb quality.
- 75 Good quality.
- 50 Normal quality.
- 10 Poor quality.

7.26.2.3 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.27 fc2JPG2Option Struct Reference

Options for saving JPEG2000 image.

Data Fields

unsigned int quality

JPEG saving quality in range (1-512).

• unsigned int reserved [16]

Reserved for future use.

7.27.1 Detailed Description

Options for saving JPEG2000 image.

7.27.2 Field Documentation

7.27.2.1 quality

unsigned int quality

JPEG saving quality in range (1-512).

7.27.2.2 reserved

unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.28 fc2LUTData Struct Reference

Information about the camera's look up table.

Data Fields

BOOL supported

Flag indicating if LUT is supported.

· BOOL enabled

Flag indicating if LUT is enabled.

unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

• unsigned int numChannels

The number of LUT channels per bank available.

• unsigned int inputBitDepth

The input bit depth of the LUT.

unsigned int outputBitDepth

The output bit depth of the LUT.

• unsigned int numEntries

The number of entries in the LUT.

• unsigned int reserved [8]

Reserved for future use.

7.28.1 Detailed Description

Information about the camera's look up table.

7.28.2 Field Documentation

7.28.2.1 enabled

BOOL enabled

Flag indicating if LUT is enabled.

7.28.2.2 inputBitDepth

unsigned int inputBitDepth

The input bit depth of the LUT.

7.28.2.3 numBanks

unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

7.28.2.4 numChannels

unsigned int numChannels

The number of LUT channels per bank available.

7.28.2.5 numEntries

unsigned int numEntries

The number of entries in the LUT.

7.28.2.6 outputBitDepth unsigned int outputBitDepth The output bit depth of the LUT. 7.28.2.7 reserved unsigned int reserved[8] Reserved for future use. 7.28.2.8 supported BOOL supported Flag indicating if LUT is supported. The documentation for this struct was generated from the following file: • FlyCapture2Defs_C.h 7.29 fc2MACAddress Struct Reference

MAC address.

Data Fields

• unsigned char octets [6]

7.29.1 Detailed Description

MAC address.

7.29.2 Field Documentation

7.29.2.1 octets

```
unsigned char octets[6]
```

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.30 fc2MJPGOption Struct Reference

Options for saving MJPG files.

Data Fields

float frameRate

Frame rate of the stream.

• unsigned int quality

Image quality (1-100)

• unsigned int reserved [256]

7.30.1 Detailed Description

Options for saving MJPG files.

7.30.2 Field Documentation

7.30.2.1 frameRate

float frameRate

Frame rate of the stream.

7.30.2.2 quality

unsigned int quality

Image quality (1-100)

7.30.2.3 reserved

```
unsigned int reserved[256]
```

The documentation for this struct was generated from the following file:

• FlyCapture2VideoDefs_C.h

7.31 fc2PGMOption Struct Reference

Options for saving PGM images.

Data Fields

· BOOL binaryFile

Whether to save the PPM as a binary file.

• unsigned int reserved [16]

Reserved for future use.

7.31.1 Detailed Description

Options for saving PGM images.

7.31.2 Field Documentation

7.31.2.1 binaryFile

```
BOOL binaryFile
```

Whether to save the PPM as a binary file.

7.31.2.2 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.32 fc2PGRGuid Struct Reference

A GUID to the camera.

Data Fields

• unsigned int value [4]

7.32.1 Detailed Description

A GUID to the camera.

It is used to uniquely identify a camera.

7.32.2 Field Documentation

7.32.2.1 value

```
unsigned int value[4]
```

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.33 fc2PNGOption Struct Reference

Options for saving PNG images.

Data Fields

BOOL interlaced

Whether to save the PNG as interlaced.

- unsigned int compressionLevel
 - Compression level (0-9).
- unsigned int reserved [16]

Reserved for future use.

7.33.1 Detailed Description

Options for saving PNG images.

7.33.2 Field Documentation

7.33.2.1 compressionLevel

unsigned int compressionLevel

Compression level (0-9).

0 is no compression, 9 is best compression.

7.33.2.2 interlaced

BOOL interlaced

Whether to save the PNG as interlaced.

7.33.2.3 reserved

unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.34 fc2PPMOption Struct Reference

Options for saving PPM images.

Data Fields

• BOOL binaryFile

Whether to save the PPM as a binary file.

• unsigned int reserved [16]

Reserved for future use.

7.34.1 Detailed Description

Options for saving PPM images.

7.34.2 Field Documentation

7.34.2.1 binaryFile

BOOL binaryFile

Whether to save the PPM as a binary file.

7.34.2.2 reserved

unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.35 fc2StrobeControl Struct Reference

A camera strobe.

Data Fields

- unsigned int source
 - Source value.
- · BOOL onOff

Flag controlling on/off.

- · unsigned int polarity
 - Signal polarity.
- · float delay

Signal delay (in ms).

· float duration

Signal duration (in ms).

• unsigned int reserved [8]

Reserved for future use.

7.35.1 Detailed Description

A camera strobe.

7.35.2 Field Documentation

| 7.35.2.1 delay |
|--------------------------|
| float delay |
| Signal delay (in ms). |
| |
| |
| 7.35.2.2 duration |
| float duration |
| Signal duration (in ms). |
| |
| 7.07.0.0 |
| 7.35.2.3 onOff |
| BOOL onOff |
| Flag controlling on/off. |
| |
| 7.35.2.4 polarity |
| 7.00.2.4 politiky |
| unsigned int polarity |
| Signal polarity. |
| |
| 7.35.2.5 reserved |
| unsigned int reserved[8] |
| Reserved for future use. |
| |

7.35.2.6 source

unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.36 fc2Strobelnfo Struct Reference

A camera strobe property.

Data Fields

· unsigned int source

Source value.

· BOOL present

Presence of strobe.

• BOOL readOutSupported

Flag indicating if strobe value can be read out.

• BOOL onOffSupported

Flag indicating if on/off is supported.

BOOL polaritySupported

Flag indicating if polarity is supported.

• float minValue

Minimum value.

float maxValue

Maximum value.

• unsigned int reserved [8]

Reserved for future use.

7.36.1 Detailed Description

A camera strobe property.

7.36.2 Field Documentation

7.36.2.1 maxValue

float maxValue

Maximum value.

| 7.36.2.2 minValue |
|---|
| float minValue |
| Minimum value. |
| |
| |
| 7.36.2.3 onOffSupported |
| BOOL onOffSupported |
| Flag indicating if on/off is supported. |
| |
| 7.00.0.4 melanihuftungantad |
| 7.36.2.4 polaritySupported |
| BOOL polaritySupported |
| Flag indicating if polarity is supported. |
| |
| 7.36.2.5 present |
| |
| BOOL present |
| Presence of strobe. |
| |
| 7.36.2.6 readOutSupported |
| DOOT, was down Gummant and |
| BOOL readOutSupported |
| Flag indicating if strabe value can be read out |
| Flag indicating if strobe value can be read out. |
| Flag indicating if strobe value can be read out. |
| Flag indicating if strobe value can be read out. 7.36.2.7 reserved |
| |
| 7.36.2.7 reserved |

7.36.2.8 source

unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.37 fc2SystemInfo Struct Reference

Description of the system.

Data Fields

fc2OSType osType

Operating system type as described by OSType.

char osDescription [MAX_STRING_LENGTH]

Detailed description of the operating system.

• fc2ByteOrder byteOrder

Byte order of the system.

• size_t sysMemSize

Amount of memory available on the system.

char cpuDescription [MAX_STRING_LENGTH]

Detailed description of the CPU.

size_t numCpuCores

Number of cores on all CPUs on the system.

• char driverList [MAX_STRING_LENGTH]

List of drivers used.

char libraryList [MAX_STRING_LENGTH]

List of libraries used.

• char gpuDescription [MAX_STRING_LENGTH]

Detailed description of the GPU.

• size_t screenWidth

Screen resolution width in pixels.

size_t screenHeight

Screen resolution height in pixels.

• unsigned int reserved [16]

Reserved for future use.

7.37.1 Detailed Description

Description of the system.

7.37.2 Field Documentation

7.37.2.1 byteOrder fc2ByteOrder byteOrder Byte order of the system. 7.37.2.2 cpuDescription char cpuDescription[MAX_STRING_LENGTH] Detailed description of the CPU. 7.37.2.3 driverList char driverList[MAX_STRING_LENGTH] List of drivers used. 7.37.2.4 gpuDescription char gpuDescription[MAX_STRING_LENGTH] Detailed description of the GPU. 7.37.2.5 libraryList

Generated by Doxygen

List of libraries used.

char libraryList[MAX_STRING_LENGTH]

7.37.2.6 numCpuCores

```
size_t numCpuCores
```

Number of cores on all CPUs on the system.

7.37.2.7 osDescription

```
char osDescription[MAX_STRING_LENGTH]
```

Detailed description of the operating system.

7.37.2.8 osType

```
fc2OSType osType
```

Operating system type as described by OSType.

7.37.2.9 reserved

```
unsigned int reserved[16]
```

Reserved for future use.

7.37.2.10 screenHeight

```
size_t screenHeight
```

Screen resolution height in pixels.

7.37.2.11 screenWidth

size_t screenWidth

Screen resolution width in pixels.

7.37.2.12 sysMemSize

```
size_t sysMemSize
```

Amount of memory available on the system.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.38 fc2TIFFOption Struct Reference

Options for saving TIFF images.

Data Fields

• fc2TIFFCompressionMethod compression

Compression method to use for encoding TIFF images.

• unsigned int reserved [16]

Reserved for future use.

7.38.1 Detailed Description

Options for saving TIFF images.

7.38.2 Field Documentation

7.38.2.1 compression

 ${\tt fc2TIFFCompressionMethod\ compression}$

Compression method to use for encoding TIFF images.

7.38.2.2 reserved

unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

FlyCapture2Defs_C.h

7.39 fc2TimeStamp Struct Reference

Timestamp information.

Data Fields

- long long seconds
 - Seconds.
- unsigned int microSeconds
 - Microseconds.
- unsigned int cycleSeconds
 - 1394 cycle time seconds.
- unsigned int cycleCount
 - 1394 cycle time count.
- unsigned int cycleOffset
 - 1394 cycle time offset.
- unsigned int reserved [8]

Reserved for future use.

7.39.1 Detailed Description

Timestamp information.

7.39.2 Field Documentation

7.39.2.1 cycleCount

unsigned int cycleCount

1394 cycle time count.

7.39.2.2 cycleOffset

unsigned int cycleOffset

1394 cycle time offset.

7.39.2.3 cycleSeconds unsigned int cycleSeconds 1394 cycle time seconds. 7.39.2.4 microSeconds unsigned int microSeconds Microseconds. 7.39.2.5 reserved unsigned int reserved[8] Reserved for future use. 7.39.2.6 seconds long long seconds Seconds. The documentation for this struct was generated from the following file: • FlyCapture2Defs_C.h

7.40 fc2TriggerDelay Struct Reference

A specific camera property.

Data Fields

• fc2PropertyType type

Property info type.

BOOL present

Flag indicating if the property is present.

BOOL absControl

Flag controlling absolute mode (real world units) or non-absolute mode (camera internal units).

· BOOL onePush

Flag controlling one push.

· BOOL onOff

Flag controlling on/off.

• BOOL autoManualMode

Flag controlling auto.

· unsigned int valueA

Value A (integer).

· unsigned int valueB

Value B (integer).

· float absValue

Floating point value.

• unsigned int reserved [8]

Reserved for future use.

7.40.1 Detailed Description

A specific camera property.

For example, to set the gain to 12dB, set the following values:

- type GAIN
- absControl true
- onePush false
- onOff-true
- autoManualMode false
- absValue 12.0

7.40.2 Field Documentation

7.40.2.1 absControl

BOOL absControl

Flag controlling absolute mode (real world units) or non-absolute mode (camera internal units).

| 7.40.2.2 absValue |
|--|
| float absValue |
| Floating point value. |
| Used to configure properties in absolute mode. |
| 7.40.2.3 autoManualMode |
| BOOL autoManualMode |
| Flag controlling auto. |
| |
| 7.40.2.4 onePush |
| BOOL onePush |
| Flag controlling one push. |
| |
| 7.40.2.5 onOff |
| BOOL onOff |
| Flag controlling on/off. |
| |
| 7.40.2.6 present |
| BOOL present |
| Flag indicating if the property is present. |
| |
| 7.40.2.7 reserved |
| unsigned int reserved[8] |
| Reserved for future use. |

7.40.2.8 type

fc2PropertyType type

Property info type.

7.40.2.9 valueA

unsigned int valueA

Value A (integer).

Used to configure properties in non-absolute mode.

7.40.2.10 valueB

unsigned int valueB

Value B (integer).

For white balance, value B applies to the blue value and value A applies to the red value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.41 fc2TriggerDelayInfo Struct Reference

Information about a specific camera property.

Data Fields

fc2PropertyType type

Property info type.

BOOL present

Flag indicating if the property is present.

· BOOL autoSupported

Flag indicating if auto is supported.

• BOOL manualSupported

Flag indicating if manual is supported.

• BOOL onOffSupported

Flag indicating if on/off is supported.

BOOL onePushSupported

Flag indicating if one push is supported.

• BOOL absValSupported

Flag indicating if absolute mode is supported.

BOOL readOutSupported

Flag indicating if property value can be read out.

• unsigned int min

Minimum value (as an integer).

unsigned int max

Maximum value (as an integer).

float absMin

Minimum value (as a floating point value).

float absMax

Maximum value (as a floating point value).

• char pUnits [MAX_STRING_LENGTH]

Textual description of units.

char pUnitAbbr [MAX_STRING_LENGTH]

Abbreviated textual description of units.

• unsigned int reserved [8]

Reserved for future use.

7.41.1 Detailed Description

Information about a specific camera property.

This structure is also also used as the TriggerDelayInfo structure.

7.41.2 Field Documentation

7.41.2.1 absMax

float absMax

Maximum value (as a floating point value).

7.41.2.2 absMin

float absMin

Minimum value (as a floating point value).

7.41.2.3 absValSupported

BOOL absValSupported

Flag indicating if absolute mode is supported.

7.41.2.4 autoSupported

BOOL autoSupported

Flag indicating if auto is supported.

7.41.2.5 manualSupported

BOOL manualSupported

Flag indicating if manual is supported.

7.41.2.6 max

unsigned int max

Maximum value (as an integer).

7.41.2.7 min

unsigned int min

Minimum value (as an integer).

7.41.2.8 onePushSupported

 ${\tt BOOL}$ onePushSupported

Flag indicating if one push is supported.

7.41.2.9 onOffSupported

BOOL onOffSupported

Flag indicating if on/off is supported.

```
7.41.2.10 present
BOOL present
Flag indicating if the property is present.
7.41.2.11 pUnitAbbr
char pUnitAbbr[MAX_STRING_LENGTH]
Abbreviated textual description of units.
7.41.2.12 pUnits
char pUnits[MAX_STRING_LENGTH]
Textual description of units.
7.41.2.13 readOutSupported
BOOL readOutSupported
Flag indicating if property value can be read out.
7.41.2.14 reserved
```

unsigned int reserved[8]

Reserved for future use.

7.41.2.15 type

fc2PropertyType type

Property info type.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.42 fc2TriggerMode Struct Reference

A camera trigger.

Data Fields

BOOL onOff

Flag controlling on/off.

· unsigned int polarity

Polarity value.

• unsigned int source

Source value.

• unsigned int mode

Mode value.

• unsigned int parameter

Parameter value.

• unsigned int reserved [8]

Reserved for future use.

7.42.1 Detailed Description

A camera trigger.

7.42.2 Field Documentation

7.42.2.1 mode

unsigned int mode

Mode value.

7.42.2.2 onOff

BOOL onOff

Flag controlling on/off.

7.42.2.3 parameter unsigned int parameter Parameter value. 7.42.2.4 polarity unsigned int polarity Polarity value. 7.42.2.5 reserved unsigned int reserved[8] Reserved for future use. 7.42.2.6 source unsigned int source Source value. The documentation for this struct was generated from the following file:

7.43 fc2TriggerModeInfo Struct Reference

Information about a camera trigger property.

• FlyCapture2Defs_C.h

Data Fields

• BOOL present

Presence of trigger mode.

BOOL readOutSupported

Flag indicating if trigger value can be read out.

· BOOL onOffSupported

Flag indicating if on/off is supported.

BOOL polaritySupported

Flag indicating if polarity is supported.

· BOOL valueReadable

Flag indicating if the value is readable.

• unsigned int sourceMask

Source mask.

BOOL softwareTriggerSupported

Flag indicating if software trigger is supported.

unsigned int modeMask

Mode mask.

• unsigned int reserved [8]

Reserved for future use.

7.43.1 Detailed Description

Information about a camera trigger property.

7.43.2 Field Documentation

7.43.2.1 modeMask

unsigned int modeMask

Mode mask.

7.43.2.2 onOffSupported

BOOL onOffSupported

Flag indicating if on/off is supported.

7.43.2.3 polaritySupported

 ${\tt BOOL}\ {\tt polaritySupported}$

Flag indicating if polarity is supported.

7.43.2.4 present

BOOL present

Presence of trigger mode.

7.43.2.5 readOutSupported

BOOL readOutSupported

Flag indicating if trigger value can be read out.

7.43.2.6 reserved

unsigned int reserved[8]

Reserved for future use.

7.43.2.7 softwareTriggerSupported

 ${\tt BOOL} \ {\tt softwareTriggerSupported}$

Flag indicating if software trigger is supported.

7.43.2.8 sourceMask

unsigned int sourceMask

Source mask.

7.43.2.9 valueReadable

BOOL valueReadable

Flag indicating if the value is readable.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

7.44 fc2Version Struct Reference

The current version of the library.

Data Fields

- unsigned int major
 - Major version number.
- unsigned int minor
 - Minor version number.
- unsigned int type
 - Type version number.
- · unsigned int build

Build version number.

7.44.1 Detailed Description

The current version of the library.

7.44.2 Field Documentation

7.44.2.1 build

unsigned int build

Build version number.

7.44.2.2 major
unsigned int major
Major version number.

7.44.2.3 minor
unsigned int minor
Minor version number.

7.44.2.4 type
unsigned int type

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h


Type version number.

Chapter 8

File Documentation

8.1 FlyCapture2_C.h File Reference

Include dependency graph for FlyCapture2 C.h:



Functions

- FLYCAPTURE2_C_API fc2Error fc2CreateContext (fc2Context *pContext)
 - Create a FC2 context for IIDC camera.
- FLYCAPTURE2_C_API fc2Error fc2CreateGigEContext (fc2Context *pContext)
 - Create a FC2 context for a GigE Vision camera.
- FLYCAPTURE2_C_API fc2Error fc2DestroyContext (fc2Context context)
 - Destroy the FC2 context.

Fire a bus reset.

- FLYCAPTURE2_C_API fc2Error fc2FireBusReset (fc2Context context, fc2PGRGuid *pGuid)
- FLYCAPTURE2_C_API fc2Error fc2GetNumOfCameras (fc2Context context, unsigned int *pNumCameras)

Gets the number of cameras attached to the PC.

FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIPAddress (fc2Context context, fc2IPAddress ip
 — Address, fc2PGRGuid *pGuid)

Gets the PGRGuid for a camera with the specified IPv4 address.

 FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIndex (fc2Context context, unsigned int index, fc2PG← RGuid *pGuid)

Gets the PGRGuid for a camera on the PC.

FLYCAPTURE2_C_API fc2Error fc2GetCameraFromSerialNumber (fc2Context context, unsigned int serial
 — Number, fc2PGRGuid *pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2_C_API fc2Error fc2GetCameraSerialNumberFromIndex (fc2Context context, unsigned int index, unsigned int *pSerialNumber)

Gets the serial number of the camera with the specified index.

• FLYCAPTURE2_C_API fc2Error fc2GetInterfaceTypeFromGuid (fc2Context context, fc2PGRGuid *pGuid, fc2InterfaceType *pInterfaceType)

Gets the interface type associated with a PGRGuid.

- FLYCAPTURE2_C_API fc2Error fc2GetNumOfDevices (fc2Context context, unsigned int *pNumDevices)

 Gets the number of devices.
- FLYCAPTURE2_C_API fc2Error fc2GetDeviceFromIndex (fc2Context context, unsigned int index, fc2PGR
 Guid *pGuid)

Gets the PGRGuid for a device.

• FLYCAPTURE2_C_API fc2Error fc2ReadPhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int *pValue)

Read a phy register on the specified device.

 FLYCAPTURE2_C_API fc2Error fc2WritePhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)

Write a phy register on the specified device.

 FLYCAPTURE2_C_API fc2Error fc2GetUsbLinkInfo (fc2Context context, fc2PGRGuid guid, unsigned int *pValue)

Read usb link info for the port that the specified device is connected to.

FLYCAPTURE2_C_API fc2Error fc2GetUsbPortStatus (fc2Context context, fc2PGRGuid guid, unsigned int *pValue)

Read usb port status for the port that the specified device is connected to.

• FLYCAPTURE2_C_API fc2Error fc2GetTopology (fc2Context context, fc2TopologyNodeContext *p↔ TopologyNodeContext)

Gets the topology information for the PC.

• FLYCAPTURE2_C_API fc2Error fc2RegisterCallback (fc2Context context, fc2BusEventCallback enum ← Callback, fc2BusCallbackType callbackType, void *pParameter, fc2CallbackHandle *pCallbackHandle)

Register a callback function that will be called when the specified callback event occurs.

FLYCAPTURE2_C_API fc2Error fc2UnregisterCallback (fc2Context context, fc2CallbackHandle callback
 Handle)

Unregister a callback function.

FLYCAPTURE2_C_API fc2Error fc2RescanBus (fc2Context context)

Force a rescan of the buses.

FLYCAPTURE2_C_API fc2Error fc2ForceIPAddressToCamera (fc2Context context, fc2MACAddress mac
 — Address, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

FLYCAPTURE2_C_API fc2Error fc2ForceAllIPAddressesAutomatically ()

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

• FLYCAPTURE2 C API fc2Error fc2ForceIPAddressAutomatically (unsigned int serialNumber)

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

FLYCAPTURE2_C_API fc2Error fc2DiscoverGigECameras (fc2Context context, fc2CameraInfo *gigE← Cameras, unsigned int *arraySize)

Discover all cameras connected to the network even if they reside on a different subnet.

FLYCAPTURE2_C_API fc2Error fc2IsCameraControlable (fc2Context context, fc2PGRGuid *pGuid, BOOL *pControlable)

Query whether a GigE camera is controllable.

• FLYCAPTURE2 C API fc2Error fc2Connect (fc2Context context, fc2PGRGuid *guid)

Connects the fc2Context to the camera specified by the GUID.

FLYCAPTURE2 C API fc2Error fc2Disconnect (fc2Context context)

Disconnects the fc2Context from the camera.

• FLYCAPTURE2_C_API BOOL fc2IsConnected (fc2Context context)

Checks if the fc2Context is connected to a physical camera specified by a GUID.

FLYCAPTURE2_C_API fc2Error fc2SetCallback (fc2Context context, fc2ImageEventCallback pCallbackFn, void *pCallbackData)

Sets the callback data to be used on completion of image transfer.

FLYCAPTURE2_C_API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

• FLYCAPTURE2_C_API fc2Error fc2StartCaptureCallback (fc2Context context, fc2ImageEventCallback p← CallbackFn, void *pCallbackData)

Starts isochronous image capture.

• FLYCAPTURE2 C API fc2Error fc2StartSyncCapture (unsigned int numCameras, fc2Context *pContexts)

Starts synchronized isochronous image capture on multiple cameras.

FLYCAPTURE2_C_API fc2Error fc2StartSyncCaptureCallback (unsigned int numCameras, fc2Context *p←
 Contexts, fc2ImageEventCallback *pCallbackFns, void **pCallbackDataArray)

Starts synchronized isochronous image capture on multiple cameras.

FLYCAPTURE2_C_API fc2Error fc2RetrieveBuffer (fc2Context context, fc2Image *pImage)

Retrieves the next image object containing the next image.

FLYCAPTURE2_C_API fc2Error fc2StopCapture (fc2Context context)

Stops isochronous image transfer and cleans up all associated resources.

FLYCAPTURE2_C_API fc2Error fc2WaitForBufferEvent (fc2Context context, fc2Image *pImage, unsigned int eventNumber)

Retrieves the next image event containing the next part of the image.

• FLYCAPTURE2_C_API fc2Error fc2SetUserBuffers (fc2Context context, unsigned char *const ppMem← Buffers, int size, int nNumBuffers)

Specify user allocated buffers to use as image data buffers.

FLYCAPTURE2_C_API fc2Error fc2GetConfiguration (fc2Context context, fc2Config *config)

Get the configuration associated with the camera.

FLYCAPTURE2 C API fc2Error fc2SetConfiguration (fc2Context context, fc2Config *config)

Set the configuration associated with the camera.

• FLYCAPTURE2 C API fc2Error fc2GetCameraInfo (fc2Context context, fc2CameraInfo *pCameraInfo)

Retrieves information from the camera such as serial number, model name and other camera information.

FLYCAPTURE2_C_API fc2Error fc2GetPropertyInfo (fc2Context context, fc2PropertyInfo *propInfo)

Retrieves information about the specified camera property.

FLYCAPTURE2_C_API fc2Error fc2GetProperty (fc2Context context, fc2Property *prop)

Reads the settings for the specified property from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetProperty (fc2Context context, fc2Property *prop)

Writes the settings for the specified property to the camera.

FLYCAPTURE2_C_API fc2Error fc2SetPropertyBroadcast (fc2Context context, fc2Property *prop)

Writes the settings for the specified property to the camera.

 FLYCAPTURE2_C_API fc2Error fc2GetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int *pDirection)

Get the GPIO pin direction for the specified pin.

FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirectionBroadcast (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

Retrieve trigger information from the camera.

FLYCAPTURE2_C_API fc2Error fc2GetTriggerMode (fc2Context context, fc2TriggerMode *triggerMode)
 Retrieve current trigger settings from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetTriggerMode (fc2Context context, fc2TriggerMode *triggerMode)

Set the specified trigger settings to the camera.

 FLYCAPTURE2_C_API fc2Error fc2SetTriggerModeBroadcast (fc2Context context, fc2TriggerMode *triggerMode)

Set the specified trigger settings to the camera.

FLYCAPTURE2 C API fc2Error fc2FireSoftwareTrigger (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2 C API fc2Error fc2FireSoftwareTriggerBroadcast (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelayInfo (fc2Context context, fc2TriggerDelayInfo *trigger
 — DelayInfo)

Retrieve trigger delay information from the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelay (fc2Context context, fc2TriggerDelay *triggerDelay)

*Retrieve current trigger delay settings from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelay (fc2Context context, fc2TriggerDelay *triggerDelay)

Set the specified trigger delay settings to the camera.

 FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelayBroadcast (fc2Context context, fc2TriggerDelay *triggerDelay)

Set the specified trigger delay settings to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetStrobeInfo (fc2Context context, fc2StrobeInfo *strobeInfo)

Retrieve strobe information from the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetStrobe (fc2Context context, fc2StrobeControl *strobeControl)

Retrieve current strobe settings from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetStrobe (fc2Context context, fc2StrobeControl *strobeControl)

Set current strobe settings to the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetStrobeBroadcast (fc2Context context, fc2StrobeControl *strobe ← Control)

Set current strobe settings to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetLUTInfo (fc2Context context, fc2LUTData *pData)

Query if LUT support is available on the camera.

 FLYCAPTURE2_C_API fc2Error fc2GetLUTBankInfo (fc2Context context, unsigned int bank, BOOL *p↔ ReadSupported, BOOL *pWriteSupported)

Query the read/write status of a single LUT bank.

• FLYCAPTURE2_C_API fc2Error fc2GetActiveLUTBank (fc2Context context, unsigned int *pActiveBank)

Get the LUT bank that is currently being used.

• FLYCAPTURE2_C_API fc2Error fc2SetActiveLUTBank (fc2Context context, unsigned int activeBank)

Set the LUT bank that will be used.

• FLYCAPTURE2 C API fc2Error fc2EnableLUT (fc2Context context, BOOL on)

Enable or disable LUT functionality on the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)

Get the LUT channel settings from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)

Set the LUT channel settings to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannel (fc2Context context, unsigned int *pCurrent ← Channel)

Retrieve the current memory channel from the camera.

- FLYCAPTURE2_C_API fc2Error fc2SaveToMemoryChannel (fc2Context context, unsigned int channel)

 Save the current settings to the specified current memory channel.
- FLYCAPTURE2_C_API fc2Error fc2RestoreFromMemoryChannel (fc2Context context, unsigned int channel)

 Restore the specified current memory channel.
- FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannelInfo (fc2Context context, unsigned int *pNum← Channels)

Query the camera for memory channel support.

FLYCAPTURE2_C_API fc2Error fc2GetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo *pInfo)

Get the current status of the embedded image information register, as well as the availability of each embedded property.

FLYCAPTURE2_C_API fc2Error fc2SetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo *pInfo)

Sets the on/off values of the embedded image information structure to the camera.

FLYCAPTURE2_C_API fc2Error fc2WriteRegister (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera.

 FLYCAPTURE2_C_API fc2Error fc2ReadRegister (fc2Context context, unsigned int address, unsigned int *pValue)

Read the specified register from the camera.

FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera with broadcast.

• FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int *pBuffer, unsigned int length)

Write to the specified register block on the camera.

 FLYCAPTURE2_C_API fc2Error fc2ReadRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int *pBuffer, unsigned int length)

Write to the specified register block on the camera.

• FLYCAPTURE2_C_API const char * fc2GetRegisterString (unsigned int registerVal)

Returns a text representation of the register value.

- FLYCAPTURE2_C_API fc2Error fc2GetCycleTime (fc2Context context, fc2TimeStamp *pTimeStamp)
 Get cycle time from camera.
- FLYCAPTURE2_C_API fc2Error fc2GetStats (fc2Context context, fc2CameraStats *pCameraStats)
- Returns the camera diagnostic information.

 FLYCAPTURE2 C API fc2Error ResetStats ()
- FLYCAPTURE2_C_API fc2Error fc2RegisterEvent (fc2Context context, fc2EventOptions *pOpts)

Register the camera to issue a custom callback function call for a specific device event.

• FLYCAPTURE2_C_API fc2Error fc2DeregisterEvent (fc2Context context, fc2EventOptions *pOpts)

De-register an event previously registered with the camera.

• FLYCAPTURE2_C_API fc2Error fc2RegisterAllEvents (fc2Context context, fc2EventOptions *pOpts)

Register the camera to issue a custom callback function call for a specific device event.

- FLYCAPTURE2_C_API fc2Error fc2DeregisterAllEvents (fc2Context context)
- FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRateInfo (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL *pSupported)

Query the camera to determine if the specified video mode and frame rate is supported.

 FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRate (fc2Context context, fc2VideoMode *videoMode, fc2FrameRate *frameRate)

Get the current video mode and frame rate from the camera.

FLYCAPTURE2_C_API fc2Error fc2SetVideoModeAndFrameRate (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetFormat7Info (fc2Context context, fc2Format7Info *info, BOOL *p
 — Supported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

• FLYCAPTURE2_C_API fc2Error fc2ValidateFormat7Settings (fc2Context context, fc2Format7ImageSettings *imageSettings, BOOL *settingsAreValid, fc2Format7PacketInfo *packetInfo)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

FLYCAPTURE2_C_API fc2Error fc2GetFormat7Configuration (fc2Context context, fc2Format7Image
 — Settings *imageSettings, unsigned int *packetSize, float *percentage)

Get the current Format7 configuration from the camera.

 FLYCAPTURE2_C_API fc2Error fc2SetFormat7ConfigurationPacket (fc2Context context, fc2Format7← ImageSettings *imageSettings, unsigned int packetSize)

Set the current Format7 configuration to the camera.

 FLYCAPTURE2_C_API fc2Error fc2SetFormat7Configuration (fc2Context context, fc2Format7ImageSettings *imageSettings, float percentSpeed)

Set the current Format7 configuration to the camera.

FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegister (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register.

FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register with broadcast.

FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegister (fc2Context context, unsigned int address, unsigned int *pValue)

Read a GVCP register.

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBlock (fc2Context context, unsigned int address, const unsigned int *pBuffer, unsigned int length)

Write a GVCP register block.

• FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegisterBlock (fc2Context context, unsigned int address, unsigned int *pBuffer, unsigned int length)

Read a GVCP register block.

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPMemory (fc2Context context, unsigned int address, const unsigned char *pBuffer, unsigned int length)

Write a GVCP memory block.

FLYCAPTURE2_C_API fc2Error fc2ReadGVCPMemory (fc2Context context, unsigned int address, unsigned char *pBuffer, unsigned int length)

Read a GVCP memory block.

- FLYCAPTURE2_C_API fc2Error fc2GetGigEProperty (fc2Context context, fc2GigEProperty *pGigEProp)

 Get the specified GigEProperty.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEProperty (fc2Context context, const fc2GigEProperty *pGigE←
 Prop)

Set the specified GigEProperty.

- FLYCAPTURE2_C_API fc2Error fc2DiscoverGigEPacketSize (fc2Context context, unsigned int *packetSize)

 Discover the largest packet size that works for the network link between the PC and the camera.
- FLYCAPTURE2_C_API fc2Error fc2QueryGigElmagingMode (fc2Context context, fc2Mode mode, BOOL *isSupported)

Check if the particular imaging mode is supported by the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImagingMode (fc2Context context, fc2Mode *mode)

Get the current imaging mode on the camera.

FLYCAPTURE2 C API fc2Error fc2SetGigEImagingMode (fc2Context context, fc2Mode mode)

Set the current imaging mode to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettingsInfo (fc2Context context, fc2GigEImage
 — SettingsInfo *pInfo)

Get information about the image settings possible on the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettings (fc2Context context, fc2GigEImageSettings *p← ImageSettings)

Get the current image settings on the camera.

FLYCAPTURE2_C_API fc2Error fc2SetGigEImageSettings (fc2Context context, const fc2GigEImageSettings *pImageSettings)

Set the image settings specified to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageBinningSettings (fc2Context context, unsigned int *horz
 — BinnningValue, unsigned int *vertBinnningValue)

Get the current binning settings on the camera.

FLYCAPTURE2_C_API fc2Error fc2SetGigEImageBinningSettings (fc2Context context, unsigned int horz
 —
 BinnningValue, unsigned int vertBinnningValue)

Set the specified binning values to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetNumStreamChannels (fc2Context context, unsigned int *num← Channels)

Get the number of stream channels present on the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel *pChannel)

Get the stream channel information for the specified channel.

• FLYCAPTURE2_C_API fc2Error fc2SetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel *pChannel)

Set the stream channel information for the specified channel.

• FLYCAPTURE2_C_API fc2Error fc2GetGigEConfig (fc2Context context, fc2GigEConfig *pConfig)

Get the current gige config on the camera.

FLYCAPTURE2_C_API fc2Error fc2SetGigEConfig (fc2Context context, const fc2GigEConfig *pConfig)
 Set the gige config specified to the camera.

FLYCAPTURE2_C_API fc2Error fc2SetDefaultColorProcessing (fc2ColorProcessingAlgorithm default
 — Method)

Set the default color processing algorithm.

Get the default color processing algorithm.

• FLYCAPTURE2_C_API fc2Error fc2SetDefaultOutputFormat (fc2PixelFormat format)

Set the default output pixel format.

• FLYCAPTURE2_C_API fc2Error fc2GetDefaultOutputFormat (fc2PixelFormat *pFormat)

Get the default output pixel format.

FLYCAPTURE2_C_API fc2Error fc2DetermineBitsPerPixel (fc2PixelFormat format, unsigned int *pBitsPer

 Pixel)

Calculate the bits per pixel for the specified pixel format.

FLYCAPTURE2_C_API fc2Error fc2CreateImage (fc2Image *pImage)

Create a fc2lmage.

• FLYCAPTURE2_C_API fc2Error fc2DestroyImage (fc2Image *image)

Destroy the fc2Image.

• FLYCAPTURE2_C_API fc2Error fc2SetImageDimensions (fc2Image *pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

• FLYCAPTURE2_C_API fc2Error fc2GetImageDimensions (fc2Image *pImage, unsigned int *pRows, unsigned int *pCols, unsigned int *pStride, fc2PixelFormat *pPixelFormat, fc2BayerTileFormat *pBayerFormat)

Get the image dimensions associated with the image object.

FLYCAPTURE2_C_API fc2Error fc2SetImageColorProcessing (fc2Image *pImage, fc2ColorProcessing
 Algorithm colorProc)

Set the color processing algorithm.

FLYCAPTURE2_C_API fc2Error fc2GetImageColorProcessing (fc2Image *pImage, fc2ColorProcessing ← Algorithm *pColorProc)

Get the current color processing algorithm.

FLYCAPTURE2_C_API fc2Error fc2SetImageData (fc2Image *pImage, const unsigned char *pData, unsigned int dataSize)

Set the data of the Image object.

FLYCAPTURE2 C API fc2Error fc2GetImageData (fc2Image *pImage, unsigned char **ppData)

Get a pointer to the data associated with the image.

FLYCAPTURE2_C_API fc2Error fc2GetImageMetadata (fc2Image *pImage, fc2ImageMetadata *pImage → MetaData)

Get the metadata associated with the image.

FLYCAPTURE2 C API fc2TimeStamp fc2GetImageTimeStamp (fc2Image *pImage)

Get the timestamp data associated with the image.

FLYCAPTURE2_C_API fc2Error fc2SaveImage (fc2Image *pImage, const char *pFilename, fc2ImageFile←
 Format format)

Save the image to the specified file name with the file format specified.

• FLYCAPTURE2_C_API fc2Error fc2SaveImageWithOption (fc2Image *pImage, const char *pFilename, fc2ImageFileFormat format, void *pOption)

Save the image to the specified file name with the file format specified.

- FLYCAPTURE2 C API fc2Error fc2ConvertImage (fc2Image *pImageIn, fc2Image *pImageOut)
- FLYCAPTURE2_C_API fc2Error fc2ConvertImageTo (fc2PixelFormat format, fc2Image *pImageIn, fc2Image *pImageOut)

Converts the current image buffer to the specified output format and stores the result in the specified image.

FLYCAPTURE2_C_API fc2Error fc2CalculateImageStatistics (fc2Image *pImage, fc2ImageStatisticsContext *pImageStatisticsContext)

Calculate statistics associated with the image.

FLYCAPTURE2_C_API fc2Error fc2CreateImageStatistics (fc2ImageStatisticsContext *pImageStatistics← Context)

Create a statistics context.

 FLYCAPTURE2_C_API fc2Error fc2DestroyImageStatistics (fc2ImageStatisticsContext imageStatistics← Context)

Destroy a statistics context.

 FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableAll (fc2ImageStatisticsContext imageStatistics← Context)

Enable all channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsDisableAll (fc2ImageStatisticsContext imageStatisticsContext)

Disable all channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableGreyOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the grey channel.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableRGBOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the RGB channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableHSLOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the HSL channels.

FLYCAPTURE2_C_API fc2Error fc2GetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL *pEnabled)

Get the status of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2SetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled)

Set the status of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2GetChannelRange (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int *pMin, unsigned int *pMax)

Get the range of a statistics channel.

Get the range of a statistics channel.

• FLYCAPTURE2_C_API fc2Error fc2GetChannelNumPixelValues (fc2ImageStatisticsContext image ← StatisticsContext, fc2StatisticsChannel channel, unsigned int *pNumPixelValues)

Get the number of unique pixel values in the image.

FLYCAPTURE2_C_API fc2Error fc2GetChannelMean (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, float *pPixelValueMean)

Get the mean of the image.

FLYCAPTURE2_C_API fc2Error fc2GetChannelHistogram (fc2ImageStatisticsContext imageStatisticsContext imageStatisticsContext

Get the histogram for the image.

FLYCAPTURE2_C_API fc2Error fc2GetImageStatistics (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int *pRangeMin, unsigned int *pRangeMax, unsigned int *pPixelValueMin, unsigned int *pPixelValueMax, unsigned int *pNumPixelValues, float *pPixelValueMean, int *ppHistogram)

Get all statistics for the image.

FLYCAPTURE2_C_API fc2Error fc2CreateTopologyNode (fc2TopologyNodeContext *pTopologyNode ← Context)

Create a TopologyNode context.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetGuid (fc2TopologyNodeContext TopologyNode
 — Context, fc2PGRGuid *pGuid)

Get the PGRGuid associated with the node.

Get the device ID associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetNodeType (fc2TopologyNodeContext TopologyNode
 — Context, fc2NodeType *pNodeType)

Get the node type associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetInterfaceType (fc2TopologyNodeContext Topology
 — NodeContext, fc2InterfaceType *pInterfaceType)

Get the interface type associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetNumChildren (fc2TopologyNodeContext Topology
 — NodeContext, unsigned int *pNumChildNodes)

Get the number of child nodes.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeContext)

Get child node located at the specified position.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeAddChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeContext)

Add the specified TopologyNode as a child of the node.

Get the number of ports.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetPortType (fc2TopologyNodeContext TopologyNode
 — Context, unsigned int position, fc2PortType *pPortType)

Get type of port located at the specified position.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeAddPortType (fc2TopologyNodeContext TopologyNode
 — Context, fc2PortType portType)

Add the specified PortType as a port of the node.

FLYCAPTURE2_C_API BOOL fc2TopologyNodeAssignGuidToNode (fc2TopologyNodeContext Topology
 — NodeContext, fc2PGRGuid guid, int deviceId)

Assign a PGRGuid and device ID to the node.

FLYCAPTURE2_C_API BOOL fc2TopologyNodeAssignGuidToNodeEx (fc2TopologyNodeContext Topology
 — NodeContext, fc2PGRGuid guid, int deviceId, fc2NodeType nodeType)

Assign a PGRGuid, device ID and nodeType to the node.

- FLYCAPTURE2_C_API fc2Error fc2DestroyTopologyNode (fc2TopologyNodeContext TopologyNodeContext)
 Destroy a TopologyNode context.
- FLYCAPTURE2_C_API fc2Error fc2CheckDriver (const fc2PGRGuid *pGuid)

Check for driver compatibility for the given camera guid.

FLYCAPTURE2_C_API fc2Error fc2GetDriverDeviceName (const fc2PGRGuid *pGuid, char *pDevice
 — Name, size_t *deviceNameLength)

Get the driver's name for a device.

• FLYCAPTURE2_C_API fc2Error fc2GetSystemInfo (fc2SystemInfo *pSystemInfo)

Get system information.

FLYCAPTURE2_C_API fc2Error fc2GetLibraryVersion (fc2Version *pVersion)

Get library version.

FLYCAPTURE2 C API fc2Error fc2LaunchBrowser (const char *pAddress)

Launch a URL in the system default browser.

FLYCAPTURE2_C_API fc2Error fc2LaunchHelp (const char *pFileName)

Open a CHM file in the system default CHM viewer.

FLYCAPTURE2_C_API fc2Error fc2LaunchCommand (const char *pCommand)

Execute a command in the terminal.

 FLYCAPTURE2_C_API fc2Error fc2LaunchCommandAsync (const char *pCommand, fc2AsyncCommand← Callback pCallback, void *pUserData)

Execute a command in the terminal.

• FLYCAPTURE2_C_API const char * fc2ErrorToDescription (fc2Error error)

Get a string representation of an error.

8.1.1 Function Documentation

8.1.1.1 fc2CreateContext()

```
\label{eq:flycapture2_c_api fc2Error fc2CreateContext (fc2Context * pContext )} fc2Context * pContext )
```

Create a FC2 context for IIDC camera.

This call must be made before any other calls that use a context will succeed.

See also

fc2DestroyContext()

Parameters

| pContext | A pointer to the fc2Context to be created. |
|----------|--|
|----------|--|

Returns

A fc2Error indicating the success or failure of the function.

8.1.1.2 fc2CreateGigEContext()

Create a FC2 context for a GigE Vision camera.

This call must be made before any other calls that use a context will succeed.

See also

fc2DestroyContext()

Parameters

| | pContext | A pointer to the fc2Context to be created. |
|--|----------|--|
|--|----------|--|

Returns

A fc2Error indicating the success or failure of the function.

8.1.1.3 fc2DeregisterAllEvents()

8.1.1.4 fc2DeregisterEvent()

De-register an event previously registered with the camera.

Parameters

| context | The fc2Context to be used. |
|---------|---|
| pOpts | Pointer to the EventOptions structure which defines the callback function to use, the event for which |
| | to register the device, and a pointer to user data (optional) to be passed to the callback function. The callback function and user data elements of the EventOptions structure are ignored in this call, and |
| | just the event name within the structure is used with this function call. |

Returns

An Error indicating the success or failure of the function.

8.1.1.5 fc2DestroyContext()

Destroy the FC2 context.

This must be called when the user is finished with the context in order to prevent memory leaks.

See also

fc2CreateContext()

Parameters

| context | The context to be destroyed. |
|---------|------------------------------|

Returns

A fc2Error indicating the success or failure of the function.

8.1.1.6 fc2GetCycleTime()

Get cycle time from camera.

Parameters

| context | The fc2Context to be used. |
|-----------|----------------------------|
| Timestamp | struct. |

Returns

A fc2Error indicating the success or failure of the function.

8.1.1.7 fc2GetStats()

Returns the camera diagnostic information.

Parameters

| context | The fc2Context to be used. |
|--------------|--|
| pCameraStats | Pointer to the fc2CameraStats structure. |

Returns

A fc2Error indicating the success or failure of the function.

8.1.1.8 fc2RegisterAllEvents()

Register the camera to issue a custom callback function call for a specific device event.

Parameters

| context | The fc2Context to be used. |
|---------|--|
| pOpts | Pointer to the EventOptions structure which defines the callback function to use, the event for which |
| | to register the device, and a pointer to user data (optional) to be passed to the callback function. The |
| | event name element of the structure is ignored with this function call. If a single event has already |
| | been registered via RegisterEvent(), this call will fail, as the user could accidentally change the the |
| | internal callback function pointer for a queued event. The user will need to de-register all registered |
| | events, then call this function again. |

Returns

An Error indicating the success or failure of the function.

8.1.1.9 fc2RegisterEvent()

Register the camera to issue a custom callback function call for a specific device event.

Parameters

| context | The fc2Context to be used. |
|---------|---|
| pOpts | Pointer to the EventOptions structure which defines the callback function to use, the event for which |
| | to register the device, and a pointer to user data (optional) to be passed to the callback function. |

Returns


An Error indicating the success or failure of the function.

8.1.1.10 ResetStats()


```
FLYCAPTURE2_C_API fc2Error ResetStats ( )
```

8.2 FlyCapture2Defs_C.h File Reference

Include dependency graph for FlyCapture2Defs_C.h:



This graph shows which files directly or indirectly include this file:



Data Structures

· struct fc2PGRGuid

A GUID to the camera.

- struct fc2Image
- struct fc2SystemInfo

Description of the system.

struct fc2Version

The current version of the library.

• struct fc2IPAddress

IPv4 address.

struct fc2MACAddress

MAC address.

· struct fc2GigEProperty

A GigE property.

· struct fc2GigEStreamChannel

Information about a single GigE stream channel.

struct fc2GigEConfig

Configuration for a GigE camera.

struct fc2GigEImageSettingsInfo

Format 7 information for a single mode.

struct fc2GigEImageSettings

Image settings for a GigE camera.

• struct fc2Format7ImageSettings

Format 7 image settings.

struct fc2Format7Info

Format 7 information for a single mode.

• struct fc2Format7PacketInfo

Format 7 packet information.

· struct fc2Config

Configuration for a camera.

struct fc2TriggerDelayInfo

Information about a specific camera property.

struct fc2TriggerDelay

A specific camera property.

struct fc2TriggerModeInfo

Information about a camera trigger property.

struct fc2TriggerMode

A camera trigger.

• struct fc2StrobeInfo

A camera strobe property.

• struct fc2StrobeControl

A camera strobe.

struct fc2TimeStamp

Timestamp information.

• struct fc2ConfigROM

Camera configuration ROM.

struct fc2CameraInfo

Camera information.

• struct fc2EmbeddedImageInfoProperty

Properties of a single embedded image info property.

· struct fc2EmbeddedImageInfo

Properties of the possible embedded image information.

struct fc2ImageMetadata

Metadata related to an image.

struct fc2LUTData

Information about the camera's look up table.

struct fc2CameraStats

Camera diagnostic information.

struct fc2PNGOption

Options for saving PNG images.

struct fc2PPMOption

Options for saving PPM images.

• struct fc2PGMOption

Options for saving PGM images.

struct fc2TIFFOption

Options for saving TIFF images.

struct fc2JPEGOption

Options for saving JPEG image.

• struct fc2JPG2Option

Options for saving JPEG2000 image.

• struct fc2BMPOption

Options for saving Bitmap image.

struct fc2EventOptions

Options for enabling device event registration.

struct fc2EventCallbackData

Macros

- #define FALSE 0
- #define TRUE 1
- #define FULL_32BIT_VALUE 0x7FFFFFF
- #define MAX_STRING_LENGTH 512

Typedefs

- typedef int BOOL
- typedef void * fc2Context

A context to the FlyCapture2 C library.

typedef void * fc2GuiContext

A context to the FlyCapture2 C GUI library.

typedef void * fc2lmagelmpl

An internal pointer used in the fc2lmage structure.

• typedef void * fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

typedef void * fc2TopologyNodeContext

A context referring to the TopologyNode object.

- typedef void * fc2CallbackHandle
- typedef void(* fc2BusEventCallback) (void *pParameter, unsigned int serialNumber)
- typedef void(* fc2lmageEventCallback) (fc2lmage *image, void *pCallbackData)
- typedef void(* fc2AsyncCommandCallback) (fc2Error retError, void *pUserData)
- typedef void(* fc2CameraEventCallback) (void *pCallbackData)

Enumerations

```
enum fc2Error {
 FC2_ERROR_UNDEFINED = -1,
 FC2 ERROR OK,
 FC2 ERROR FAILED,
 FC2 ERROR NOT IMPLEMENTED,
 FC2 ERROR FAILED BUS MASTER CONNECTION,
 FC2 ERROR NOT CONNECTED,
 FC2_ERROR_INIT_FAILED,
 FC2_ERROR_NOT_INTITIALIZED,
 FC2 ERROR INVALID PARAMETER,
 FC2 ERROR INVALID SETTINGS,
 FC2_ERROR_INVALID_BUS_MANAGER,
 FC2_ERROR_MEMORY_ALLOCATION_FAILED,
 FC2_ERROR_LOW_LEVEL_FAILURE,
 FC2 ERROR NOT FOUND,
 FC2_ERROR_FAILED_GUID,
 FC2_ERROR_INVALID_PACKET_SIZE,
 FC2 ERROR INVALID MODE,
 FC2_ERROR_NOT_IN_FORMAT7,
 FC2_ERROR_NOT_SUPPORTED,
 FC2_ERROR_TIMEOUT,
 FC2 ERROR BUS MASTER FAILED,
 FC2_ERROR_INVALID_GENERATION,
 FC2_ERROR_LUT_FAILED,
 FC2 ERROR IIDC FAILED,
 FC2 ERROR STROBE FAILED.
 FC2_ERROR_TRIGGER_FAILED,
 FC2_ERROR_PROPERTY_FAILED,
 FC2 ERROR PROPERTY NOT PRESENT,
 FC2 ERROR REGISTER FAILED,
 FC2_ERROR_READ_REGISTER_FAILED,
 FC2_ERROR_WRITE_REGISTER_FAILED,
 FC2_ERROR_ISOCH_FAILED,
 FC2 ERROR ISOCH ALREADY STARTED,
 FC2_ERROR_ISOCH_NOT_STARTED,
 FC2_ERROR_ISOCH_START_FAILED,
 FC2 ERROR ISOCH RETRIEVE BUFFER FAILED,
 FC2_ERROR_ISOCH_STOP_FAILED,
 FC2_ERROR_ISOCH_SYNC_FAILED,
 FC2 ERROR ISOCH BANDWIDTH EXCEEDED,
 FC2 ERROR IMAGE CONVERSION FAILED,
 FC2 ERROR IMAGE LIBRARY FAILURE,
 FC2_ERROR_BUFFER_TOO_SMALL,
 FC2_ERROR_IMAGE_CONSISTENCY_ERROR,
 FC2 ERROR INCOMPATIBLE DRIVER,
 FC2 ERROR FORCE 32BITS = FULL 32BIT VALUE }
    The error types returned by functions.

    enum fc2BusCallbackType {

 FC2_BUS_RESET,
 FC2_ARRIVAL,
 FC2 REMOVAL,
 FC2_CALLBACK_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    The type of bus callback to register a callback function for.
enum fc2GrabMode {
 FC2 DROP FRAMES,
 FC2_BUFFER_FRAMES,
```

```
FC2_UNSPECIFIED_GRAB_MODE,
 FC2_GRAB_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    The grab strategy employed during image transfer.

    enum fc2GrabTimeout {

 FC2 TIMEOUT NONE = 0,
 FC2 TIMEOUT INFINITE = -1,
 FC2_TIMEOUT_UNSPECIFIED = -2,
 FC2_GRAB_TIMEOUT_FORCE_32BITS = FULL_32BIT_VALUE }
    Timeout options for grabbing images.

    enum fc2BandwidthAllocation {

 FC2 BANDWIDTH ALLOCATION OFF = 0,
 FC2 BANDWIDTH ALLOCATION ON = 1,
 FC2_BANDWIDTH_ALLOCATION_UNSUPPORTED = 2,
 FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED = 3,
 FC2 BANDWIDTH ALLOCATION FORCE 32BITS = FULL 32BIT VALUE }
    Bandwidth allocation options for 1394 devices.
enum fc2InterfaceType {
 FC2 INTERFACE IEEE1394,
 FC2 INTERFACE USB 2,
 FC2 INTERFACE USB 3,
 FC2 INTERFACE GIGE,
 FC2_INTERFACE_UNKNOWN,
 FC2_INTERFACE_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Interfaces that a camera may use to communicate with a host.
enum fc2PropertyType {
 FC2 BRIGHTNESS,
 FC2 AUTO EXPOSURE,
 FC2 SHARPNESS,
 FC2 WHITE BALANCE,
 FC2_HUE,
 FC2_SATURATION,
 FC2 GAMMA,
 FC2_IRIS,
 FC2 FOCUS,
 FC2 ZOOM,
 FC2 PAN,
 FC2_TILT,
 FC2 SHUTTER,
 FC2 GAIN,
 FC2 TRIGGER MODE,
 FC2_TRIGGER_DELAY,
 FC2_FRAME_RATE,
 FC2 TEMPERATURE,
 FC2_UNSPECIFIED_PROPERTY_TYPE,
 FC2 PROPERTY TYPE FORCE 32BITS = FULL 32BIT VALUE }
    Camera properties.
enum fc2FrameRate {
 FC2_FRAMERATE_1_875,
 FC2 FRAMERATE 3 75,
 FC2 FRAMERATE 7 5,
 FC2 FRAMERATE 15,
 FC2 FRAMERATE 30,
 FC2 FRAMERATE 60,
 FC2 FRAMERATE 120,
 FC2_FRAMERATE_240,
 FC2_FRAMERATE_FORMAT7,
```

```
FC2_NUM_FRAMERATES,
 FC2_FRAMERATE_FORCE_32BITS = FULL_32BIT_VALUE }
    Frame rates in frames per second.
enum fc2VideoMode {
 FC2_VIDEOMODE_160x120YUV444,
 FC2_VIDEOMODE_320x240YUV422,
 FC2 VIDEOMODE 640x480YUV411,
 FC2 VIDEOMODE 640x480YUV422,
 FC2_VIDEOMODE_640x480RGB,
 FC2_VIDEOMODE_640x480Y8,
 FC2_VIDEOMODE_640x480Y16,
 FC2_VIDEOMODE_800x600YUV422,
 FC2_VIDEOMODE_800x600RGB,
 FC2_VIDEOMODE_800x600Y8,
 FC2 VIDEOMODE 800x600Y16,
 FC2_VIDEOMODE_1024x768YUV422,
 FC2_VIDEOMODE_1024x768RGB,
 FC2_VIDEOMODE_1024x768Y8,
 FC2_VIDEOMODE_1024x768Y16,
 FC2_VIDEOMODE_1280x960YUV422,
 FC2_VIDEOMODE_1280x960RGB,
 FC2_VIDEOMODE_1280x960Y8,
 FC2 VIDEOMODE 1280x960Y16,
 FC2 VIDEOMODE 1600x1200YUV422,
 FC2_VIDEOMODE_1600x1200RGB,
 FC2 VIDEOMODE 1600x1200Y8,
 FC2_VIDEOMODE_1600x1200Y16,
 FC2_VIDEOMODE_FORMAT7,
 FC2_NUM_VIDEOMODES,
 FC2_VIDEOMODE_FORCE_32BITS = FULL_32BIT_VALUE }
    DCAM video modes.
enum fc2Mode {
 FC2 MODE 0 = 0,
 FC2_MODE_1,
 FC2_MODE_2,
 FC2 MODE 3,
 FC2 MODE 4,
 FC2_MODE_5,
 FC2_MODE_6,
 FC2 MODE 7,
 FC2_MODE_8,
 FC2 MODE 9,
 FC2 MODE 10,
 FC2 MODE 11,
 FC2_MODE_12,
 FC2_MODE_13,
 FC2_MODE_14,
 FC2 MODE 15,
 FC2_MODE_16,
 FC2_MODE_17,
 FC2 MODE 18,
 FC2_MODE_19,
 FC2_MODE_20,
 FC2 MODE 21,
 FC2 MODE 22,
 FC2 MODE 23,
 FC2_MODE_24,
 FC2_MODE_25,
```

```
FC2 MODE 26,
 FC2 MODE 27,
 FC2 MODE 28,
 FC2_MODE_29,
 FC2 MODE 30,
 FC2 MODE 31,
 FC2 NUM MODES.
 FC2 MODE FORCE 32BITS = FULL 32BIT VALUE }
    Camera modes for DCAM formats as well as Format7.
enum fc2PixelFormat {
 FC2 PIXEL FORMAT MONO8 = 0x80000000,
 FC2_PIXEL_FORMAT_411YUV8 = 0x40000000,
 FC2_PIXEL_FORMAT_422YUV8 = 0x200000000,
 FC2 PIXEL FORMAT 444YUV8 = 0x10000000,
 FC2_PIXEL_FORMAT_RGB8 = 0x08000000,
 FC2 PIXEL FORMAT MONO16 = 0x04000000,
 FC2 PIXEL FORMAT RGB16 = 0x02000000,
 FC2 PIXEL FORMAT S MONO16 = 0x01000000,
 FC2_PIXEL_FORMAT_S_RGB16 = 0x00800000,
 FC2_PIXEL_FORMAT_RAW8 = 0x00400000
 FC2 PIXEL FORMAT RAW16 = 0x00200000,
 FC2_PIXEL_FORMAT_MONO12 = 0x00100000,
 FC2_PIXEL_FORMAT_RAW12 = 0x00080000,
 FC2_PIXEL_FORMAT_BGR = 0x80000008,
 FC2 PIXEL FORMAT BGRU = 0x40000008,
 FC2 PIXEL FORMAT RGB = FC2 PIXEL FORMAT RGB8,
 FC2_PIXEL_FORMAT_RGBU = 0x40000002,
 FC2 PIXEL FORMAT BGR16 = 0x02000001,
 FC2 PIXEL FORMAT BGRU16 = 0x02000002,
 FC2_PIXEL_FORMAT_422YUV8_JPEG = 0x40000001,
 FC2_NUM_PIXEL_FORMATS = 20,
 FC2_UNSPECIFIED_PIXEL_FORMAT = 0 }
    Pixel formats available for Format7 modes.

    enum fc2BusSpeed {

 FC2 BUSSPEED S100,
 FC2 BUSSPEED S200,
 FC2 BUSSPEED S400.
 FC2 BUSSPEED S480,
 FC2_BUSSPEED_S800,
 FC2_BUSSPEED_S1600,
 FC2 BUSSPEED S3200,
 FC2_BUSSPEED_S5000,
 FC2_BUSSPEED_10BASE_T,
 FC2 BUSSPEED 100BASE T,
 FC2 BUSSPEED 1000BASE T,
 FC2_BUSSPEED_10000BASE_T,
 FC2_BUSSPEED_S_FASTEST,
 FC2 BUSSPEED ANY,
 FC2 BUSSPEED SPEED UNKNOWN = -1,
 FC2_BUSSPEED_FORCE_32BITS = FULL_32BIT_VALUE }
    Bus speeds.

    enum fc2PCleBusSpeed {

 FC2 PCIE BUSSPEED 2 5,
 FC2_PCIE_BUSSPEED_5_0,
 FC2 PCIE BUSSPEED UNKNOWN = -1,
 FC2 PCIE BUSSPEED FORCE 32BITS = FULL 32BIT VALUE }
enum fc2DriverType {
 FC2_DRIVER_1394_CAM,
```

```
FC2_DRIVER_1394_PRO,
 FC2 DRIVER 1394 JUJU,
 FC2_DRIVER_1394_VIDEO1394,
 FC2_DRIVER_1394_RAW1394,
 FC2_DRIVER_USB_NONE,
 FC2 DRIVER USB CAM,
 FC2 DRIVER USB3 PRO,
 FC2_DRIVER_GIGE_NONE,
 FC2 DRIVER GIGE FILTER,
 FC2 DRIVER GIGE PRO,
 FC2_DRIVER_GIGE_LWF,
 FC2_DRIVER_UNKNOWN = -1,
 FC2_DRIVER_FORCE_32BITS = FULL_32BIT_VALUE }
    Types of low level drivers that FlyCapture uses.

    enum fc2ColorProcessingAlgorithm {

 FC2 DEFAULT.
 FC2_NO_COLOR_PROCESSING,
 FC2_NEAREST_NEIGHBOR_FAST,
 FC2 EDGE SENSING,
 FC2_HQ_LINEAR,
 FC2_RIGOROUS,
 FC2_IPP,
 FC2_DIRECTIONAL,
 FC2 WEIGHTED DIRECTIONAL,
 FC2_COLOR_PROCESSING_ALGORITHM_FORCE_32BITS = FULL_32BIT_VALUE }
    Color processing algorithms.
enum fc2BayerTileFormat {
 FC2_BT_NONE,
 FC2 BT RGGB,
 FC2 BT GRBG,
 FC2 BT GBRG,
 FC2_BT_BGGR,
 FC2 BT FORCE 32BITS = FULL 32BIT VALUE }
    Bayer tile formats.
enum fc2lmageFileFormat {
 FC2\_FROM\_FILE\_EXT = -1,
 FC2 PGM,
 FC2 PPM,
 FC2 BMP,
 FC2 JPEG,
 FC2 JPEG2000,
 FC2_TIFF,
 FC2 PNG,
 FC2 RAW,
 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS = FULL_32BIT_VALUE }
    File formats to be used for saving images to disk.

    enum fc2GigEPropertyType {

 FC2 HEARTBEAT,
 FC2_HEARTBEAT_TIMEOUT,
 PACKET_SIZE,
 PACKET_DELAY }
    Possible properties that can be queried from the camera.
enum fc2StatisticsChannel {
 FC2 STATISTICS GREY,
 FC2 STATISTICS RED,
 FC2_STATISTICS_GREEN,
 FC2_STATISTICS_BLUE,
```

```
FC2_STATISTICS_HUE,
 FC2 STATISTICS SATURATION,
 FC2_STATISTICS_LIGHTNESS,
 FC2_STATISTICS_FORCE_32BITS = FULL_32BIT_VALUE }
    Channels that allow statistics to be calculated.
enum fc2OSType {
 FC2_WINDOWS_X86,
 FC2 WINDOWS X64,
 FC2 LINUX X86,
 FC2_LINUX_X64,
 FC2_MAC,
 FC2 UNKNOWN OS,
 FC2 OSTYPE FORCE 32BITS = FULL 32BIT VALUE }
    Possible operating systems.
enum fc2ByteOrder {
 FC2_BYTE_ORDER_LITTLE_ENDIAN,
 FC2_BYTE_ORDER_BIG_ENDIAN,
 FC2_BYTE_ORDER_FORCE_32BITS = FULL_32BIT_VALUE }
    Possible byte orders.
enum fc2PortType {
 NOT CONNECTED = 1,
 CONNECTED_TO_PARENT,
 CONNECTED_TO_CHILD }
    Possible states of a port on a node.
enum fc2NodeType {
 COMPUTER,
 BUS,
 CAMERA,
 NODE }
    Type of node.
• enum fc2TIFFCompressionMethod {
 FC2 TIFF NONE = 1,
 FC2 TIFF PACKBITS,
 FC2_TIFF_DEFLATE,
 FC2_TIFF_ADOBE_DEFLATE,
 FC2_TIFF_CCITTFAX3,
 FC2_TIFF_CCITTFAX4,
 FC2_TIFF_LZW,
 FC2_TIFF_JPEG }
```

8.2.1 Enumeration Type Documentation

8.2.1.1 fc2ByteOrder

enum fc2ByteOrder

Possible byte orders.

Enumerator

| FC2_BYTE_ORDER_LITTLE_ENDIAN | |
|------------------------------|--|
| FC2_BYTE_ORDER_BIG_ENDIAN | |
| FC2_BYTE_ORDER_FORCE_32BITS | |

8.2.1.2 fc2NodeType

enum fc2NodeType

Type of node.

Enumerator

| COMPUTER | |
|----------|--|
| BUS | |
| CAMERA | |
| NODE | |

8.2.1.3 fc2OSType

enum fc2OSType

Possible operating systems.

Enumerator

| FC2_WINDOWS_X86 | All Windows 32-bit variants. |
|-------------------------|------------------------------|
| FC2_WINDOWS_X64 | All Windows 64-bit variants. |
| FC2_LINUX_X86 | All Linux 32-bit variants. |
| FC2_LINUX_X64 | All Linux 32-bit variants. |
| FC2_MAC | Mac OSX. |
| FC2_UNKNOWN_OS | Unknown operating system. |
| FC2_OSTYPE_FORCE_32BITS | |

8.2.1.4 fc2PortType

enum fc2PortType

Possible states of a port on a node.

Enumerator

| NOT_CONNECTED | |
|---------------------|--|
| CONNECTED_TO_PARENT | |
| CONNECTED_TO_CHILD | |

8.2.1.5 fc2StatisticsChannel

enum fc2StatisticsChannel


Channels that allow statistics to be calculated.

Enumerator

| FC2_STATISTICS_GREY | |
|-----------------------------|--|
| FC2_STATISTICS_RED | |
| FC2_STATISTICS_GREEN | |
| FC2_STATISTICS_BLUE | |
| FC2_STATISTICS_HUE | |
| FC2_STATISTICS_SATURATION | |
| FC2_STATISTICS_LIGHTNESS | |
| FC2_STATISTICS_FORCE_32BITS | |

8.3 FlyCapture2GUI_C.h File Reference

Include dependency graph for FlyCapture2GUI_C.h:



Functions

- FLYCAPTURE2_C_API fc2Error fc2CreateGUIContext (fc2GuiContext *pContext)

 Create a GUI context.
- FLYCAPTURE2_C_API fc2Error fc2DestroyGUIContext (fc2GuiContext context)
 Destroy a GUI context.
- FLYCAPTURE2_C_API void fc2GUIConnect (fc2GuiContext context, fc2Context cameraContext)

Connect GUI context to a camera context.

FLYCAPTURE2_C_API void fc2GUIDisconnect (fc2GuiContext context)

Disconnect GUI context from camera.

FLYCAPTURE2_C_API void fc2Disonnect (fc2GuiContext context) __attribute__((deprecated))

Disconnect GUI context from camera.

• FLYCAPTURE2_C_API void fc2Show (fc2GuiContext context)

Show the GUI.

• FLYCAPTURE2_C_API void fc2Hide (fc2GuiContext context)

Hide the GUI.

• FLYCAPTURE2_C_API BOOL fc2IsVisible (fc2GuiContext context)

Check if the GUI is visible.

• FLYCAPTURE2_C_API void fc2ShowModal (fc2GuiContext context, BOOL *pOkSelected, fc2PGRGuid *guidArray, unsigned int *size)

Show the camera selection dialog.

8.3.1 Function Documentation

8.3.1.1 fc2CreateGUIContext()

Create a GUI context.

Any GigE cameras that were connected prior to this call will lose CCP after the call. Consider creating a GUI context prior to connecting any GigE cameras or calling connect on any outstanding GigE camera context.

Parameters

| pContext | Pointer to context to be created. |
|----------|-----------------------------------|

Returns

An Error indicating the success or failure of the function.

8.3.1.2 fc2DestroyGUIContext()

Destroy a GUI context.

Parameters

| context | Context to be destroyed. |
|---------|--------------------------|
| COLLEX | Context to be destroyed. |

Returns

An Error indicating the success or failure of the function.

8.3.1.3 fc2Disonnect()

Disconnect GUI context from camera.

Parameters

| context | GUI context to disconnect. |
|---------|----------------------------|
|---------|----------------------------|

Returns

An Error indicating the success or failure of the function.

Deprecated This method is deprecated and will be removed in a future FlyCapture2 release. Please use fc2GU← IDisconnect instead.

8.3.1.4 fc2GUIConnect()

Connect GUI context to a camera context.

Parameters

| context | GUI context to connect. |
|---------------|----------------------------|
| cameraContext | Camera context to connect. |

Returns

An Error indicating the success or failure of the function.

8.3.1.5 fc2GUIDisconnect()

```
FLYCAPTURE2_C_API void fc2GUIDisconnect ( \label{fc2GuiContext} fc2GuiContext\ context\ )
```

Disconnect GUI context from camera.

Parameters

```
context | GUI context to disconnect.
```

Returns

An Error indicating the success or failure of the function.

8.3.1.6 fc2Hide()

Hide the GUI.

Parameters

Returns

An Error indicating the success or failure of the function.

8.3.1.7 fc2lsVisible()

Check if the GUI is visible.

Parameters

Returns

Whether the GUI is visible.

8.3.1.8 fc2Show()

Show the GUI.

Parameters

| now. |
|------|
| |

Returns

An Error indicating the success or failure of the function.

8.3.1.9 fc2ShowModal()


Show the camera selection dialog.

Parameters

| context | Pointer to context to show. | |
|-------------|---|--|
| pOkSelected | Whether Ok (true) or Cancel (false) was clicked. | |
| guidArray | guidArray Array of PGRGuids containing the selected cameras | |
| size | Size of PGRGuid array. | |

8.4 FlyCapture2Internal_C.h File Reference

Include dependency graph for FlyCapture2Internal_C.h:



Data Structures

- struct fc2InternalContext
- struct fc2InternalGuiContext
- struct fc2InternalImageCallback

Functions

- bool IsContextValid (fc2Context context)
- bool IsGuiContextValid (fc2GuiContext context)
- void SyncCppImageToStruct (fc2Image *pImage)

8.4.1 Function Documentation


8.4.1.1 IsContextValid()

8.4.1.2 IsGuiContextValid()

8.4.1.3 SyncCppImageToStruct()

8.5 FlyCapture2Platform_C.h File Reference

This graph shows which files directly or indirectly include this file:



Macros

- #define FLYCAPTURE2_C_API
- #define FLYCAPTURE2_C_CALL_CONVEN

8.5.1 Macro Definition Documentation

8.5.1.1 FLYCAPTURE2_C_API


#define FLYCAPTURE2_C_API

8.5.1.2 FLYCAPTURE2_C_CALL_CONVEN

#define FLYCAPTURE2_C_CALL_CONVEN

8.6 FlyCapture2Private_C.h File Reference

Include dependency graph for FlyCapture2Private_C.h:



Functions

• FLYCAPTURE2_C_API void * GetInternal (unsigned int index)


8.6.1 Function Documentation

8.6.1.1 GetInternal()

```
FLYCAPTURE2_C_API void* GetInternal (
          unsigned int index )
```

8.7 FlyCapture2Video_C.h File Reference

Include dependency graph for FlyCapture2Video_C.h:



Functions

• FLYCAPTURE2_C_API fc2Error fc2VideoCreate (fc2VideoContext *pVideoContext)

Create a Video context.

FLYCAPTURE2_C_API fc2Error fc2VideoAVIOpen (fc2VideoContext VideoContext, const char *pFileName, fc2AVIOption *pOption)

Open an AVI file in preparation for writing Images to disk.

• FLYCAPTURE2_C_API fc2Error fc2VideoMJPGOpen (fc2VideoContext VideoContext, const char *pFile → Name, fc2MJPGOption *pOption)

Open an MJPEG file in preparation for writing Images to disk.

Open an H.264 video file in preparation for writing Images to disk.

- FLYCAPTURE2_C_API fc2Error fc2VideoAppend (fc2VideoContext VideoContext, fc2Image *pImage)
 Append an image to the video file.
- FLYCAPTURE2_C_API fc2Error fc2VideoSetMaximumSize (fc2VideoContext VideoContext, unsigned int size)

Set the maximum file size (in megabytes) of a AVI/MP4 file.

• FLYCAPTURE2_C_API fc2Error fc2VideoClose (fc2VideoContext VideoContext)


Close the video file.

• FLYCAPTURE2 C API fc2Error fc2VideoDestroy (fc2VideoContext VideoContext)

Destroy a video context.

8.8 FlyCapture2VideoDefs C.h File Reference

This graph shows which files directly or indirectly include this file:



Data Structures

• struct fc2MJPGOption

Options for saving MJPG files.

• struct fc2H264Option

Options for saving H264 files.

• struct fc2AVIOption

Options for saving AVI files.


Typedefs

typedef void * fc2VideoContext
 A context referring to the video recorder object.

8.9 Licensing.dox File Reference

8.10 MultiSyncLibrary_C.h File Reference

Include dependency graph for MultiSyncLibrary C.h:



Functions

- MULTISYNCLIBRARY_C_API syncError syncCreateContext (syncContext *pContext)
 - Create a Sync context for MultiSync Library.
- MULTISYNCLIBRARY_C_API syncError syncDestroyContext (syncContext context)
 - Destory the sync context.
- MULTISYNCLIBRARY_C_API syncError syncStart (syncContext context)
 - Start the sync progress.
- MULTISYNCLIBRARY_C_API syncError syncStop (syncContext context)
 - Stop the sync progress.
- MULTISYNCLIBRARY_C_API syncError syncRescanMasterTimingBus (syncContext context)
 - Scan newly connected or removed timing bus (for corss-PC syncing only)
- MULTISYNCLIBRARY_C_API syncMessage syncGetStatus (syncContext context)
 - Start the sync progress.
- MULTISYNCLIBRARY C API double syncGetTimeSinceSynced (syncContext context)
 - Time since sync started.
- MULTISYNCLIBRARY_C_API BOOL syncIsTimingBusConnected (syncContext context)
 - Whether syncing across PCs.
- MULTISYNCLIBRARY_C_API BOOL syncEnableCrossPCSynchronization (syncContext context)
 - Enable across pc synchronization support.
- MULTISYNCLIBRARY_C_API BOOL syncDisableCrossPCSynchronization (syncContext context)
 - Disable across pc synchronization support.
- MULTISYNCLIBRARY_C_API BOOL syncQueryCrossPCSynchronizationSetting (syncContext context)
 - Query cross pc synchronizaion support status.

260 File Documentation

8.10.1 Function Documentation

8.10.1.1 syncCreateContext()

Create a Sync context for MultiSync Library.

This call must be made before any other calls that use a context will succeed.

Parameters

| pContext | A pointer to the syncContext to be created. |
|----------|---|
| poomon | repointed to the cylindeditions to be distated. |

Returns

A syncError indicating the success or failure of the function.

8.10.1.2 syncDestroyContext()

Destory the sync context.

This must be called when the user is finished with the context in order to prevent memory leaks.

Parameters

| context | The syncContext to be destoryed. |
|---------|----------------------------------|

Returns

A syncError indicating the success or failure of the function.

8.10.1.3 syncDisableCrossPCSynchronization()

Disable across pc synchronization support.

Parameters

| context | The syncContext to be used. |
|---------|-----------------------------|
|---------|-----------------------------|

Returns

True if operation was successful

8.10.1.4 syncEnableCrossPCSynchronization()

Enable across pc synchronization support.

Parameters

| | context | The syncContext to be used. |
|--|---------|-----------------------------|
|--|---------|-----------------------------|

Returns

True if operation was successful

8.10.1.5 syncGetStatus()

Start the sync progress.

Parameters

```
context The syncContext to be used.
```

Returns

A syncMessage indicating the sync status.

8.10.1.6 syncGetTimeSinceSynced()

262 File Documentation

Time since sync started.

Parameters

| context | The syncContext to be used. |
|---------|-----------------------------|
|---------|-----------------------------|

Returns

Time sinced synced.

8.10.1.7 syncIsTimingBusConnected()

Whether syncing across PCs.

Parameters

Returns

True if its syncing across PC

8.10.1.8 syncQueryCrossPCSynchronizationSetting()

Query cross pc synchronizaion support status.

Parameters

```
context The syncContext to be used.
```

Returns

True if cross pc synchronization was supported

8.10.1.9 syncRescanMasterTimingBus()

```
\begin{tabular}{ll} {\tt MULTISYNCLIBRARY\_C\_API} & syncError & syncRescanMasterTimingBus & ( \\ & syncContext & context & ) \end{tabular}
```

264 File Documentation Scan newly connected or removed timing bus (for corss-PC syncing only)

Parameters

Returns

A syncError indicating the success or failure of the function.

8.10.1.10 syncStart()

Start the sync progress.

Parameters

| context | The syncContext to be used. |
|---------|-----------------------------|
|---------|-----------------------------|

Returns

A syncError indicating the success or failure of the function.

8.10.1.11 syncStop()

Stop the sync progress.

Parameters

context The syncContext to be used.


266 File Documentation

Returns


A syncError indicating the success or failure of the function.

8.11 MultiSyncLibraryDefs_C.h File Reference

Include dependency graph for MultiSyncLibraryDefs_C.h:



This graph shows which files directly or indirectly include this file:



Macros

- #define FALSE 0
- #define TRUE 1
- #define FULL_32BIT_VALUE 0x7FFFFFF
- #define MAX_STRING_LENGTH 512

Typedefs

- typedef int BOOL
- typedef void * syncContext

A context to the MultiSync C library.

Enumerations

```
enum syncError {
 SYNC_ERROR_OK = 0,
 SYNC_ERROR_FAILED,
 SYNC_ERROR_ALREADY_STARTED,
 SYNC_ERROR_ALREADY_STOPPED,
 SYNC_ERROR_CONTEXT_NOT_INITIALIZED,
 SYNC_ERROR_UNKNOWN_ERROR }
enum syncMessage {
 SYNC_MESSAGE_OK = 0,
 SYNC_MESSAGE_FAILED,
 SYNC_MESSAGE_STARTED,
 SYNC_MESSAGE_STOPPED,
 SYNC MESSAGE SYNCING,
 SYNC_MESSAGE_NOMASTER,
 SYNC_MESSAGE_THREAD_ERROR,
 SYNC MESSAGE DEVICE ERROR,
 SYNC_MESSAGE_NOT_ENOUGH_DEVICES,
 SYNC_MESSAGE_BUS_RESET,
 SYNC_MESSAGE_NOT_INITIALIZED,
 SYNC_MESSAGE_UNKNOWN_ERROR }
```

8.11.1 Macro Definition Documentation

8.11.1.1 FALSE

#define FALSE 0

8.11.1.2 FULL_32BIT_VALUE

#define FULL_32BIT_VALUE 0x7FFFFFFF

8.11.1.3 MAX_STRING_LENGTH

#define MAX_STRING_LENGTH 512

8.11.1.4 TRUE

#define TRUE 1

268 File Documentation

8.11.2 Typedef Documentation

8.11.2.1 BOOL

typedef int BOOL

8.11.2.2 syncContext

typedef void* syncContext

A context to the MultiSync C library.

It must be created before performing any calls to the library.

8.11.3 Enumeration Type Documentation

8.11.3.1 syncError

enum syncError

Enumerator

| SYNC_ERROR_OK | |
|------------------------------------|--|
| SYNC_ERROR_FAILED | |
| SYNC_ERROR_ALREADY_STARTED | |
| SYNC_ERROR_ALREADY_STOPPED | |
| SYNC_ERROR_CONTEXT_NOT_INITIALIZED | |
| SYNC_ERROR_UNKNOWN_ERROR | |

8.11.3.2 syncMessage

enum syncMessage


Enumerator

| SYNC_MESSAGE_OK | |
|----------------------|--|
| SYNC_MESSAGE_FAILED | |
| SYNC_MESSAGE_STARTED | |

Enumerator

8.12 MultiSyncLibraryPlatform_C.h File Reference

This graph shows which files directly or indirectly include this file:



Macros

- #define MULTISYNCLIBRARY_C_API
- #define MULTISYNCLIBRARY_C_CALL_CONVEN

8.12.1 Macro Definition Documentation

8.12.1.1 MULTISYNCLIBRARY_C_API

#define MULTISYNCLIBRARY_C_API

8.12.1.2 MULTISYNCLIBRARY_C_CALL_CONVEN

#define MULTISYNCLIBRARY_C_CALL_CONVEN

270 File Documentation

Index

| absControl | fc2GetCameraSerialNumberFromIndex, 17 |
|--|---------------------------------------|
| fc2TriggerDelay, 214 | fc2GetDeviceFromIndex, 17 |
| absMax | fc2GetInterfaceTypeFromGuid, 18 |
| fc2TriggerDelayInfo, 217 | fc2GetNumOfCameras, 18 |
| absMin | fc2GetNumOfDevices, 18 |
| fc2TriggerDelayInfo, 217 | fc2GetTopology, 19 |
| absValSupported | fc2GetUsbLinkInfo, 19 |
| fc2TriggerDelayInfo, 217 | fc2GetUsbPortStatus, 20 |
| absValue | fc2lsCameraControlable, 20 |
| fc2TriggerDelay, 214 | fc2ReadPhyRegister, 21 |
| applicationIPAddress | fc2RegisterCallback, 21 |
| fc2CameraInfo, 150 | fc2RescanBus, 22 |
| applicationPort | fc2UnregisterCallback, 22 |
| fc2CameraInfo, 151 | fc2WritePhyRegister, 22 |
| asyncBusSpeed | busNumber |
| fc2Config, 160 | fc2CameraInfo, 151 |
| autoManualMode | byteOrder |
| fc2TriggerDelay, 215 | fc2SystemInfo, 209 |
| autoSupported | , |
| fc2TriggerDelayInfo, 217 | cameraCurrents |
| available | fc2CameraStats, 157 |
| fc2EmbeddedImageInfoProperty, 168 | cameraPowerUp |
| on the state of th | fc2CameraStats, 157 |
| BOOL | cameraVoltages |
| MultiSyncLibraryDefs_C.h, 268 | fc2CameraStats, 157 |
| TypeDefs, 116 | ccpStatus |
| bandwidthAllocation | fc2CameraInfo, 151 |
| fc2Config, 160 | chipIdHi |
| bayerFormat | fc2ConfigROM, 164 |
| fc2Image, 189 | chipIdLo |
| bayerTileFormat | fc2ConfigROM, 164 |
| fc2CameraInfo, 151 | cols |
| binaryFile | fc2lmage, 189 |
| fc2PGMOption, 201 | compression |
| fc2PPMOption, 204 | fc2TIFFOption, 211 |
| bitrate | compressionLevel |
| fc2H264Option, 188 | fc2PNGOption, 203 |
| brightness | configROM |
| fc2EmbeddedImageInfo, 167 | fc2CameraInfo, 151 |
| build | Connection and Image Retrieval, 25 |
| fc2Version, 224 | fc2Connect, 25 |
| Bus Manager Operation, 11 | fc2Disconnect, 26 |
| fc2DiscoverGigECameras, 12 | fc2GetConfiguration, 26 |
| fc2FireBusReset, 13 | fc2lsConnected, 27 |
| fc2ForceAllIPAddressesAutomatically, 13 | fc2RetrieveBuffer, 27 |
| fc2ForceIPAddressAutomatically, 13 | fc2SetCallback, 28 |
| fc2ForceIPAddressToCamera, 14 | fc2SetConfiguration, 28 |
| fc2GetCameraFromIPAddress, 16 | fc2SetUserBuffers, 29 |
| fc2GetCameraFromIndex, 14 | fc2StartCapture, 29 |
| fc2GetCameraFromSerialNumber, 16 | fc2StartCaptureCallback, 30 |

| fc2StartSyncCapture, 30 | fc2LUTData, 198 |
|-------------------------------------|----------------------------------|
| fc2StartSyncCaptureCallback, 31 | Enumerations, 118 |
| fc2StopCapture, 32 | fc2BandwidthAllocation, 122 |
| fc2WaitForBufferEvent, 32 | fc2BayerTileFormat, 123 |
| | - |
| cpuDescription | fc2BusCallbackType, 123 |
| fc2SystemInfo, 209 | fc2BusSpeed, 124 |
| cycleCount | fc2ColorProcessingAlgorithm, 124 |
| fc2TimeStamp, 212 | fc2DriverType, 125 |
| cycleOffset | fc2Error, 125 |
| fc2TimeStamp, 212 | fc2FrameRate, 126 |
| cycleSeconds | fc2GrabMode, 127 |
| fc2TimeStamp, 212 | fc2GrabTimeout, 127 |
| · | fc2ImageFileFormat, 128 |
| DCAM Formats, 64 | fc2InterfaceType, 128 |
| fc2GetVideoModeAndFrameRate, 64 | fc2Mode, 128 |
| fc2GetVideoModeAndFrameRateInfo, 65 | fc2PCleBusSpeed, 129 |
| fc2SetVideoModeAndFrameRate, 65 | fc2PixelFormat, 130 |
| dataSize | fc2PropertyType, 130 |
| fc2Image, 189 | |
| defaultGateway | fc2VideoMode, 131 |
| | EventCallbackFcn |
| fc2CameraInfo, 151 | fc2EventOptions, 171 |
| delay | EventData |
| fc2StrobeControl, 205 | fc2EventCallbackData, 169 |
| destinationIpAddress | EventDataSize |
| fc2GigEStreamChannel, 186 | fc2EventCallbackData, 169 |
| doNotFragment | EventID |
| fc2GigEStreamChannel, 186 | fc2EventCallbackData, 170 |
| driverList | EventName |
| fc2SystemInfo, 209 | fc2EventCallbackData, 170 |
| driverName | fc2EventOptions, 171 |
| fc2CameraInfo, 152 | EventTimestamp |
| driverType | fc2EventCallbackData, 170 |
| fc2CameraInfo, 152 | EventUserData EventUserData |
| duration | |
| fc2StrobeControl, 205 | fc2EventCallbackData, 170 |
| 1023(10becontrol, 203 | fc2EventOptions, 171 |
| embeddedBrightness | EventUserDataSize |
| • | fc2EventCallbackData, 170 |
| fc2ImageMetadata, 191 | fc2EventOptions, 171 |
| embeddedExposure | exposure |
| fc2ImageMetadata, 191 | fc2EmbeddedImageInfo, 167 |
| embeddedFrameCounter | |
| fc2ImageMetadata, 191 | FALSE |
| embeddedGPIOPinState | MultiSyncLibraryDefs_C.h, 267 |
| fc2ImageMetadata, 191 | TypeDefs, 115 |
| embeddedGain | FLYCAPTURE2_C_API |
| fc2ImageMetadata, 191 | FlyCapture2Platform_C.h, 256 |
| embeddedROIPosition | FLYCAPTURE2_C_CALL_CONVEN |
| fc2ImageMetadata, 191 | FlyCapture2Platform_C.h, 256 |
| embeddedShutter | FULL 32BIT VALUE |
| fc2ImageMetadata, 192 | MultiSyncLibraryDefs_C.h, 267 |
| embeddedStrobePattern | TypeDefs, 115 |
| | - · |
| fc2ImageMetadata, 192 | fc2AVIOption, 147 |
| embeddedTimeStamp | frameRate, 147 |
| fc2ImageMetadata, 192 | reserved, 147 |
| embeddedWhiteBalance | fc2AsyncCommandCallback |
| fc2ImageMetadata, 192 | Image saving structures., 139 |
| enablePacketResend | fc2BMPOption, 148 |
| fc2GigEConfig, 179 | indexedColor_8bit, 148 |
| enabled | reserved, 148 |

| fc2BandwidthAllocation | numCurrents, 158 |
|-------------------------------|------------------------------------|
| Enumerations, 122 | numResendPacketsReceived, 158 |
| fc2BayerTileFormat | numResendPacketsRequested, 158 |
| Enumerations, 123 | numVoltages, 158 |
| fc2BusCallbackType | portErrors, 158 |
| Enumerations, 123 | regReadFailed, 158 |
| fc2BusEventCallback | regWriteFailed, 158 |
| Image saving structures., 139 | reserved, 159 |
| fc2BusSpeed | temperature, 159 |
| Enumerations, 124 | timeSinceBusReset, 159 |
| fc2ByteOrder | timeSinceInitialization, 159 |
| FlyCapture2Defs_C.h, 248 | timeStamp, 159 |
| fc2CalculateImageStatistics | fc2CheckDriver |
| Image Operation, 86 | Utilities, 110 |
| fc2CallbackHandle | fc2ColorProcessingAlgorithm |
| Image saving structures., 139 | Enumerations, 124 |
| fc2CameraEventCallback | fc2Config, 159 |
| Image saving structures., 139 | asyncBusSpeed, 160 |
| fc2CameraInfo, 149 | bandwidthAllocation, 160 |
| applicationIPAddress, 150 | grabMode, 161 |
| applicationPort, 151 | grabTimeout, 161 |
| bayerTileFormat, 151 | highPerformanceRetrieveBuffer, 161 |
| busNumber, 151 | isochBusSpeed, 161 |
| ccpStatus, 151 | minNumImageNotifications, 161 |
| configROM, 151 | numBuffers, 162 |
| defaultGateway, 151 | numImageNotifications, 162 |
| driverName, 152 | registerTimeout, 162 |
| driverType, 152 | registerTimeoutRetries, 162 |
| firmwareBuildTime, 152 | reserved, 163 |
| firmwareVersion, 152 | fc2ConfigROM, 163 |
| gigEMajorVersion, 152 | chipIdHi, 164 |
| gigEMinorVersion, 152 | chipIdLo, 164 |
| iidcVer, 153 | nodeVendorld, 164 |
| interfaceType, 153 | pszKeyword, 164 |
| ipAddress, 153 | reserved, 164 |
| isColorCamera, 153 | unitSWVer, 165 |
| | • |
| macAddress, 153 | unitSpecId, 164 |
| maximumBusSpeed, 153 | unitSubSWVer, 165 |
| modelName, 154 | vendorUniqueInfo_0, 165 |
| nodeNumber, 154 | vendorUniqueInfo_1, 165 |
| pcieBusSpeed, 154 | vendorUniqueInfo_2, 165 |
| reserved, 154 | vendorUniqueInfo_3, 165 |
| sensorInfo, 154 | fc2Connect |
| sensorResolution, 154 | Connection and Image Retrieval, 25 |
| serialNumber, 155 | fc2Context |
| subnetMask, 155 | TypeDefs, 116 |
| userDefinedName, 155 | fc2ConvertImage |
| vendorName, 155 | Image Operation, 86 |
| xmIURL1, 155 | fc2ConvertImageTo |
| xmlURL2, 155 | Image Operation, 87 |
| fc2CameraStats, 156 | fc2CreateContext |
| cameraCurrents, 157 | FlyCapture2_C.h, 236 |
| cameraPowerUp, 157 | fc2CreateGUIContext |
| cameraVoltages, 157 | FlyCapture2GUI_C.h, 251 |
| imageCorrupt, 157 | fc2CreateGigEContext |
| imageDriverDropped, 157 | FlyCapture2_C.h, 237 |
| imageDropped, 157 | fc2CreateImage |
| imageXmitFailed, 157 | Image Operation, 87 |

| fc2CreateImageStatistics | fc2EventOptions, 171 |
|--|-------------------------------------|
| Image Statistics Operation, 96 | EventCallbackFcn, 171 |
| fc2CreateTopologyNode | EventName, 171 |
| TopologyNode Operation, 104 | EventUserData, 171 |
| fc2DeregisterAllEvents | EventUserDataSize, 171 |
| FlyCapture2_C.h, 237 | fc2FireBusReset |
| fc2DeregisterEvent | Bus Manager Operation, 13 |
| FlyCapture2_C.h, 237 | fc2FireSoftwareTrigger |
| fc2DestroyContext | Trigger, 41 |
| FlyCapture2_C.h, 238 | fc2FireSoftwareTriggerBroadcast |
| | |
| fc2DestroyGUIContext | Trigger, 42 |
| FlyCapture2GUI_C.h, 251 | fc2ForceAllIPAddressesAutomatically |
| fc2DestroyImage | Bus Manager Operation, 13 |
| Image Operation, 88 | fc2ForceIPAddressAutomatically |
| fc2DestroyImageStatistics | Bus Manager Operation, 13 |
| Image Statistics Operation, 96 | fc2ForceIPAddressToCamera |
| fc2DestroyTopologyNode | Bus Manager Operation, 14 |
| TopologyNode Operation, 104 | fc2Format7ImageSettings, 172 |
| fc2DetermineBitsPerPixel | height, 172 |
| Image Operation, 88 | mode, 172 |
| fc2Disconnect | offsetX, 173 |
| Connection and Image Retrieval, 26 | offsetY, 173 |
| fc2DiscoverGigECameras | pixelFormat, 173 |
| Bus Manager Operation, 12 | reserved, 173 |
| fc2DiscoverGigEPacketSize | width, 173 |
| GigE property manipulation, 73 | fc2Format7Info, 174 |
| fc2Disonnect | imageHStepSize, 174 |
| FlyCapture2GUI_C.h, 252 | imageVStepSize, 174 |
| fc2DriverType | maxHeight, 175 |
| Enumerations, 125 | maxPacketSize, 175 |
| | |
| fc2EmbeddedImageInfo, 166 | maxWidth, 175 |
| brightness, 167 | minPacketSize, 175 |
| exposure, 167 | mode, 175 |
| frameCounter, 167 | offsetHStepSize, 175 |
| GPIOPinState, 167 | offsetVStepSize, 176 |
| gain, 1 <mark>67</mark> | packetSize, 176 |
| ROIPosition, 167 | percentage, 176 |
| shutter, 167 | pixelFormatBitField, 176 |
| strobePattern, 168 | reserved, 176 |
| timestamp, 168 | vendorPixelFormatBitField, 176 |
| whiteBalance, 168 | fc2Format7PacketInfo, 177 |
| fc2EmbeddedImageInfoProperty, 168 | maxBytesPerPacket, 177 |
| available, 168 | recommendedBytesPerPacket, 177 |
| onOff, 169 | reserved, 178 |
| fc2EnableLUT | unitBytesPerPacket, 178 |
| Look Up Table, 51 | fc2FrameRate |
| fc2Error | Enumerations, 126 |
| Enumerations, 125 | fc2GUIConnect |
| fc2ErrorToDescription | FlyCapture2GUI_C.h, 252 |
| • | |
| Utilities, 111 fc2EventCallbackData, 169 | fc2GUIDisconnect |
| | FlyCapture2GUI_C.h, 252 |
| EventData, 169 | fc2GetActiveLUTBank |
| EventDataSize, 169 | Look Up Table, 52 |
| EventID, 170 | fc2GetCameraFromIPAddress |
| EventName, 170 | Bus Manager Operation, 16 |
| EventTimestamp, 170 | fc2GetCameraFromIndex |
| EventUserData, 170 | Bus Manager Operation, 14 |
| EventUserDataSize, 170 | fc2GetCameraFromSerialNumber |
| | |

| Bus Manager Operation, 16 | Image Operation, 91 |
|--|---|
| fc2GetCameraInfo | fc2GetImageStatistics |
| Information and Properties, 34 | Image Statistics Operation, 99 |
| fc2GetCameraSerialNumberFromIndex | fc2GetImageTimeStamp |
| Bus Manager Operation, 17 | Image Operation, 91 |
| fc2GetChannelHistogram | fc2GetInterfaceTypeFromGuid |
| Image Statistics Operation, 96 | Bus Manager Operation, 18 |
| fc2GetChannelMean | fc2GetLUTBankInfo |
| Image Statistics Operation, 97 | Look Up Table, 52 |
| fc2GetChannelNumPixelValues | fc2GetLUTChannel |
| Image Statistics Operation, 97 | Look Up Table, 53 |
| fc2GetChannelPixelValueRange | fc2GetLUTInfo |
| Image Statistics Operation, 98 | Look Up Table, 53 |
| fc2GetChannelRange | fc2GetLibraryVersion |
| Image Statistics Operation, 98 | Utilities, 111 |
| fc2GetChannelStatus | fc2GetMemoryChannel |
| Image Statistics Operation, 99 | Memory Channels, 57 |
| fc2GetConfiguration | fc2GetMemoryChannelInfo |
| Connection and Image Retrieval, 26 | Memory Channels, 57 |
| fc2GetCycleTime | fc2GetNumOfCameras |
| | |
| FlyCapture2_C.h, 238 | Bus Manager Operation, 18 fc2GetNumOfDevices |
| fc2GetDefaultColorProcessing | |
| Image Operation, 88 | Bus Manager Operation, 18 fc2GetNumStreamChannels |
| fc2GetDefaultOutputFormat | |
| Image Operation, 89 fc2GetDeviceFromIndex | GigE image stream configuration, 83 |
| | fc2GetProperty |
| Bus Manager Operation, 17 | Information and Properties, 34 |
| fc2GetDriverDeviceName | fc2GetPropertyInfo |
| Utilities, 111 | Information and Properties, 35 |
| fc2GetEmbeddedImageInfo | fc2GetRegisterString |
| Memory Channels, 56 | Register Operation, 60 |
| fc2GetFormat7Configuration | fc2GetStats |
| Format7, 66 | FlyCapture2_C.h, 239 |
| fc2GetFormat7Info | fc2GetStrobe |
| Format7, 67 | Strobe, 48 |
| fc2GetGPIOPinDirection | fc2GetStrobeInfo |
| General Purpose Input / Output, 38 | Strobe, 49 |
| fc2GetGigEConfig | fc2GetSystemInfo |
| GigE image stream configuration, 82 | Utilities, 112 |
| fc2GetGigEImageBinningSettings | fc2GetTopology |
| GigE image binning settings, 80 | Bus Manager Operation, 19 |
| fc2GetGigEImageSettings | fc2GetTriggerDelay |
| GigE image settings, 75 | Trigger, 42 |
| fc2GetGigEImageSettingsInfo | fc2GetTriggerDelayInfo |
| GigE image settings, 76 | Trigger, 43 |
| fc2GetGigEImagingMode | fc2GetTriggerMode |
| GigE image settings, 76 | Trigger, 43 |
| fc2GetGigEProperty | fc2GetTriggerModeInfo |
| GigE property manipulation, 73 | Trigger, 44 |
| fc2GetGigEStreamChannelInfo | fc2GetUsbLinkInfo |
| GigE image stream configuration, 82 | Bus Manager Operation, 19 |
| fc2GetImageColorProcessing | fc2GetUsbPortStatus |
| Image Operation, 89 | Bus Manager Operation, 20 |
| fc2GetImageData | fc2GetVideoModeAndFrameRate |
| Image Operation, 90 | DCAM Formats, 64 |
| fc2GetImageDimensions | fc2GetVideoModeAndFrameRateInfo |
| Image Operation, 90 | DCAM Formats, 65 |
| fc2GetImageMetadata | fc2GigEConfig, 178 |

| enablePacketResend, 179 | cols, 189 |
|---------------------------------|------------------------------------|
| registerTimeout, 179 | dataSize, 189 |
| registerTimeoutRetries, 179 | format, 189 |
| reserved, 179 | imageImpl, 189 |
| fc2GigEImageSettings, 179 | pData, 189 |
| height, 180 | receivedDataSize, 190 |
| offsetX, 180 | rows, 190 |
| offsetY, 180 | stride, 190 |
| pixelFormat, 180 | fc2ImageEventCallback |
| reserved, 181 | Image saving structures., 139 |
| width, 181 | fc2ImageFileFormat |
| fc2GigEImageSettingsInfo, 181 | Enumerations, 128 |
| imageHStepSize, 182 | fc2ImageImpl |
| imageVStepSize, 182 | TypeDefs, 116 |
| maxHeight, 182 | fc2ImageMetadata, 190 |
| maxWidth, 182 | embeddedBrightness, 191 |
| offsetHStepSize, 182 | embeddedExposure, 191 |
| offsetVStepSize, 182 | embeddedFrameCounter, 191 |
| pixelFormatBitField, 183 | embeddedGPIOPinState, 191 |
| reserved, 183 | embeddedGain, 191 |
| vendorPixelFormatBitField, 183 | embeddedROIPosition, 191 |
| fc2GigEProperty, 183 | embeddedShutter, 192 |
| | embeddedStrobePattern, 192 |
| isReadable, 184 | • |
| isWritable, 184 | embeddedTimeStamp, 192 |
| max, 184 | embeddedWhiteBalance, 192 |
| min, 184 | reserved, 192 |
| propType, 184 | fc2ImageStatisticsContext |
| reserved, 184 | TypeDefs, 116 |
| value, 185 | fc2ImageStatisticsDisableAll |
| fc2GigEPropertyType | Image Statistics Operation, 100 |
| GigE specific enumerations, 133 | fc2ImageStatisticsEnableAll |
| fc2GigEStreamChannel, 185 | Image Statistics Operation, 100 |
| destinationIpAddress, 186 | fc2ImageStatisticsEnableGreyOnly |
| doNotFragment, 186 | Image Statistics Operation, 100 |
| hostPort, 186 | fc2ImageStatisticsEnableHSLOnly |
| interPacketDelay, 186 | Image Statistics Operation, 101 |
| networkInterfaceIndex, 186 | fc2ImageStatisticsEnableRGBOnly |
| packetSize, 186 | Image Statistics Operation, 101 |
| reserved, 187 | fc2InterfaceType |
| sourcePort, 187 | Enumerations, 128 |
| fc2GrabMode | fc2InternalContext, 193 |
| Enumerations, 127 | pBusMgr, 193 |
| fc2GrabTimeout | pCamera, 193 |
| Enumerations, 127 | fc2InternalGuiContext, 193 |
| fc2GuiContext | pCameraControlDlg, 193 |
| TypeDefs, 116 | pCameraSelectionDlg, 193 |
| fc2H264Option, 187 | fc2InternalImageCallback, 194 |
| bitrate, 188 | pCallback, 194 |
| frameRate, 188 | pCallbackData, 194 |
| height, 188 | fc2IsCameraControlable |
| reserved, 188 | Bus Manager Operation, 20 |
| width, 188 | fc2IsConnected |
| fc2Hide | Connection and Image Retrieval, 27 |
| FlyCapture2GUI_C.h, 253 | fc2lsVisible |
| fc2IPAddress, 195 | FlyCapture2GUI_C.h, 253 |
| octets, 195 | fc2JPEGOption, 195 |
| fc2Image, 189 | progressive, 196 |
| bayerFormat, 189 | quality, 196 |
| , | 1 2/ |

| reserved, 196 | GVCP Register Operation, 70 |
|---|--|
| fc2JPG2Option, 196 | fc2ReadGVCPRegisterBlock |
| quality, 197 | GVCP Register Operation, 70 |
| reserved, 197 | fc2ReadPhyRegister |
| fc2LUTData, 197 | Bus Manager Operation, 21 |
| enabled, 198 | fc2ReadRegister |
| inputBitDepth, 198 | Register Operation, 60 |
| numBanks, 198 | fc2ReadRegisterBlock |
| numChannels, 198 | Register Operation, 61 |
| numEntries, 198 | fc2RegisterAllEvents |
| outputBitDepth, 198 | FlyCapture2_C.h, 239 |
| reserved, 199 | fc2RegisterCallback |
| supported, 199 | Bus Manager Operation, 21 |
| fc2LaunchBrowser | fc2RegisterEvent |
| Utilities, 112 | FlyCapture2_C.h, 239 |
| fc2LaunchCommand | fc2RescanBus |
| Utilities, 113 | Bus Manager Operation, 22 |
| fc2LaunchCommandAsync | fc2RestoreFromMemoryChannel |
| Utilities, 113 | Memory Channels, 58 |
| fc2LaunchHelp | fc2RetrieveBuffer |
| Utilities, 113 | Connection and Image Retrieval, 27 |
| fc2MACAddress, 199 | fc2SaveImage |
| octets, 199 | Image Operation, 91 |
| fc2MJPGOption, 200 | fc2SaveImageWithOption |
| frameRate, 200 | Image Operation, 92 |
| quality, 200 | fc2SaveToMemoryChannel |
| reserved, 200 | Memory Channels, 58 |
| fc2Mode | fc2SetActiveLUTBank |
| Enumerations, 128 | Look Up Table, 54 |
| fc2NodeType | fc2SetCallback |
| FlyCapture2Defs_C.h, 249 | Connection and Image Retrieval, 28 |
| fc2OSType | fc2SetChannelStatus |
| FlyCapture2Defs C.h, 249 | Image Statistics Operation, 102 |
| fc2PCleBusSpeed | fc2SetConfiguration |
| Enumerations, 129 | Connection and Image Retrieval, 28 |
| fc2PGMOption, 201 | fc2SetDefaultColorProcessing |
| binaryFile, 201 | Image Operation, 92 |
| reserved, 201 | fc2SetDefaultOutputFormat |
| fc2PGRGuid, 202 | Image Operation, 93 |
| value, 202 | fc2SetEmbeddedImageInfo |
| fc2PNGOption, 202 | Memory Channels, 59 |
| compressionLevel, 203 | fc2SetFormat7Configuration |
| interlaced, 203 | Format7, 67 |
| | |
| recerved 203 | fc2SetFormat7ConfigurationPacket |
| reserved, 203 | fc2SetFormat7ConfigurationPacket |
| fc2PPMOption, 203 | Format7, 67 |
| fc2PPMOption, 203 binaryFile, 204 | Format7, 67 fc2SetGPIOPinDirection |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 fc2PropertyType | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 fc2SetGigEImageBinningSettings |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 fc2PropertyType Enumerations, 130 | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 fc2SetGigEImageBinningSettings GigE image binning settings, 80 |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 fc2PropertyType Enumerations, 130 fc2QueryGigEImagingMode | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 fc2SetGigEImageBinningSettings GigE image binning settings, 80 fc2SetGigEImageSettings |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 fc2PropertyType Enumerations, 130 fc2QueryGigEImagingMode GigE image settings, 76 | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 fc2SetGigEImageBinningSettings GigE image binning settings, 80 fc2SetGigEImageSettings GigE image settings, 78 |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 fc2PropertyType Enumerations, 130 fc2QueryGigEImagingMode GigE image settings, 76 fc2ReadGVCPMemory | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 fc2SetGigEImageBinningSettings GigE image binning settings, 80 fc2SetGigEImageSettings GigE image settings, 78 fc2SetGigEImagingMode |
| fc2PPMOption, 203 binaryFile, 204 reserved, 204 fc2PixelFormat Enumerations, 130 fc2PortType FlyCapture2Defs_C.h, 249 fc2PropertyType Enumerations, 130 fc2QueryGigEImagingMode GigE image settings, 76 | Format7, 67 fc2SetGPIOPinDirection General Purpose Input / Output, 39 fc2SetGPIOPinDirectionBroadcast General Purpose Input / Output, 39 fc2SetGigEConfig GigE image stream configuration, 83 fc2SetGigEImageBinningSettings GigE image binning settings, 80 fc2SetGigEImageSettings GigE image settings, 78 |

| GigE property manipulation, 74 | polaritySupported, 207 |
|-------------------------------------|--|
| | |
| fc2SetGigEStreamChannelInfo | present, 207 |
| GigE image stream configuration, 84 | readOutSupported, 207 |
| fc2SetImageColorProcessing | reserved, 207 |
| Image Operation, 93 | source, 207 |
| fc2SetImageData | fc2SystemInfo, 208 |
| Image Operation, 93 | byteOrder, 209 |
| fc2SetImageDimensions | cpuDescription, 209 |
| Image Operation, 94 | driverList, 209 |
| fc2SetLUTChannel | gpuDescription, 209 |
| Look Up Table, 54 | libraryList, 209 |
| fc2SetProperty | numCpuCores, 209 |
| Information and Properties, 36 | osDescription, 210 |
| | osType, 210 |
| fc2SetPropertyBroadcast | |
| Information and Properties, 36 | reserved, 210 |
| fc2SetStrobe | screenHeight, 210 |
| Strobe, 49 | screenWidth, 210 |
| fc2SetStrobeBroadcast | sysMemSize, 210 |
| Strobe, 50 | fc2TIFFCompressionMethod |
| fc2SetTriggerDelay | Image saving structures., 139 |
| Trigger, 44 | fc2TIFFOption, 211 |
| fc2SetTriggerDelayBroadcast | compression, 211 |
| Trigger, 45 | reserved, 211 |
| fc2SetTriggerMode | fc2TimeStamp, 212 |
| Trigger, 45 | cycleCount, 212 |
| | - |
| fc2SetTriggerModeBroadcast | cycleOffset, 212 |
| Trigger, 46 | cycleSeconds, 212 |
| fc2SetUserBuffers | microSeconds, 213 |
| Connection and Image Retrieval, 29 | reserved, 213 |
| fc2SetVideoModeAndFrameRate | seconds, 213 |
| DCAM Formats, 65 | fc2TopologyNodeAddChild |
| fc2Show | TopologyNode Operation, 104 |
| FlyCapture2GUI_C.h, 253 | fc2TopologyNodeAddPortType |
| fc2ShowModal | TopologyNode Operation, 105 |
| FlyCapture2GUI_C.h, 254 | fc2TopologyNodeAssignGuidToNode |
| fc2StartCapture | TopologyNode Operation, 105 |
| Connection and Image Retrieval, 29 | fc2TopologyNodeAssignGuidToNodeEx |
| fc2StartCaptureCallback | TopologyNode Operation, 106 |
| · | |
| Connection and Image Retrieval, 30 | fc2TopologyNodeContext |
| fc2StartSyncCapture | TypeDefs, 117 |
| Connection and Image Retrieval, 30 | fc2TopologyNodeGetChild |
| fc2StartSyncCaptureCallback | TopologyNode Operation, 106 |
| Connection and Image Retrieval, 31 | fc2TopologyNodeGetDeviceId |
| fc2StatisticsChannel | TopologyNode Operation, 106 |
| FlyCapture2Defs_C.h, 250 | fc2TopologyNodeGetGuid |
| fc2StopCapture | TopologyNode Operation, 107 |
| Connection and Image Retrieval, 32 | fc2TopologyNodeGetInterfaceType |
| fc2StrobeControl, 204 | TopologyNode Operation, 107 |
| delay, 205 | fc2TopologyNodeGetNodeType |
| | TopologyNode Operation, 108 |
| duration, 205 | |
| onOff, 205 | fc2TopologyNodeGetNumChildren |
| polarity, 205 | TopologyNode Operation, 108 |
| reserved, 205 | fc2TopologyNodeGetNumPorts |
| source, 205 | |
| (00) (000 | TopologyNode Operation, 108 |
| fc2StrobeInfo, 206 | |
| maxValue, 206 | TopologyNode Operation, 108 |
| | TopologyNode Operation, 108 fc2TopologyNodeGetPortType |

| absValue, 214 | TypeDefs, 117 |
|---------------------------------|------------------------------------|
| autoManualMode, 215 | fc2VideoCreate |
| onOff, 215 | Video Recording Operation, 142 |
| onePush, 215 | fc2VideoDestroy |
| present, 215 | Video Recording Operation, 143 |
| reserved, 215 | fc2VideoH264Open |
| type, 215 | Video Recording Operation, 143 |
| valueA, 216 | fc2VideoMJPGOpen |
| valueB, 216 | Video Recording Operation, 144 |
| fc2TriggerDelayInfo, 216 | fc2VideoMode |
| absMax, 217 | Enumerations, 131 |
| absMin, 217 | fc2VideoSetMaximumSize |
| absValSupported, 217 | Video Recording Operation, 144 |
| autoSupported, 217 | fc2WaitForBufferEvent |
| manualSupported, 218 | Connection and Image Retrieval, 32 |
| max, 218 | fc2WriteGVCPMemory |
| min, 218 | GVCP Register Operation, 71 |
| onOffSupported, 218 | fc2WriteGVCPRegister |
| onePushSupported, 218 | GVCP Register Operation, 71 |
| · | |
| pUnitAbbr, 219 | fc2WriteGVCPRegisterBlock |
| pUnits, 219 | GVCP Register Operation, 71 |
| present, 218 | fc2WriteGVCPRegisterBroadcast |
| readOutSupported, 219 | GVCP Register Operation, 72 |
| reserved, 219 | fc2WritePhyRegister |
| type, 219 | Bus Manager Operation, 22 |
| fc2TriggerMode, 220 | fc2WriteRegister |
| mode, 220 | Register Operation, 62 |
| onOff, 220 | fc2WriteRegisterBlock |
| parameter, 220 | Register Operation, 62 |
| polarity, 221 | fc2WriteRegisterBroadcast |
| reserved, 221 | Register Operation, 63 |
| source, 221 | firmwareBuildTime |
| fc2TriggerModeInfo, 221 | fc2CameraInfo, 152 |
| modeMask, 222 | firmwareVersion |
| onOffSupported, 222 | fc2CameraInfo, 152 |
| polaritySupported, 222 | FlyCapture2_C.h, 227 |
| present, 223 | fc2CreateContext, 236 |
| readOutSupported, 223 | fc2CreateGigEContext, 237 |
| reserved, 223 | fc2DeregisterAllEvents, 237 |
| software Trigger Supported, 223 | fc2DeregisterEvent, 237 |
| sourceMask, 223 | fc2DestroyContext, 238 |
| valueReadable, 223 | fc2GetCycleTime, 238 |
| fc2UnregisterCallback | fc2GetStats, 239 |
| Bus Manager Operation, 22 | fc2RegisterAllEvents, 239 |
| fc2ValidateFormat7Settings | fc2RegisterEvent, 239 |
| Format7, 68 | ResetStats, 240 |
| fc2Version, 224 | FlyCapture2Defs C.h, 240 |
| build, 224 | fc2ByteOrder, 248 |
| major, 224 | fc2NodeType, 249 |
| minor, 225 | fc2OSType, 249 |
| type, 225 | fc2PortType, 249 |
| fc2VideoAVIOpen | fc2StatisticsChannel, 250 |
| | |
| Video Recording Operation, 142 | FlyCapture2GUI_C.h, 250 |
| fc2VideoAppend | fc2CreateGUIContext, 251 |
| Video Recording Operation, 141 | fc2DestroyGUIContext, 251 |
| fc2VideoClose | fc2Disonnect, 252 |
| Video Recording Operation, 142 | fc2GUIConnect, 252 |
| fc2VideoContext | fc2GUIDisconnect, 252 |
| | |

| fc2Hide, 253 | fc2GetGigEConfig, 82 |
|--|--|
| fc2IsVisible, 253 | fc2GetGigEStreamChannelInfo, 82 |
| fc2Show, 253 | fc2GetNumStreamChannels, 83 |
| fc2ShowModal, 254 | fc2SetGigEConfig, 83 |
| FlyCapture2Internal_C.h, 255 | fc2SetGigEStreamChannelInfo, 84 |
| IsContextValid, 255 | GigE property manipulation, 73 |
| IsGuiContextValid, 255 | fc2DiscoverGigEPacketSize, 73 |
| SyncCppImageToStruct, 255 | fc2GetGigEProperty, 73 |
| FlyCapture2Platform_C.h, 256 | fc2SetGigEProperty, 74 |
| FLYCAPTURE2 C API, 256 | GigE specific enumerations, 133 |
| FLYCAPTURE2 C CALL CONVEN, 256 | fc2GigEPropertyType, 133 |
| FlyCapture2Private_C.h, 257 | GigE specific structures, 136 |
| | • |
| GetInternal, 257 | gigEMajorVersion |
| FlyCapture2Video_C.h, 257 | fc2CameraInfo, 152 |
| FlyCapture2VideoDefs_C.h, 258 | gigEMinorVersion |
| format | fc2CameraInfo, 152 |
| fc2Image, 189 | gpuDescription |
| Format7, 66 | fc2SystemInfo, 209 |
| fc2GetFormat7Configuration, 66 | grabMode |
| fc2GetFormat7Info, 67 | fc2Config, 161 |
| fc2SetFormat7Configuration, 67 | grabTimeout |
| fc2SetFormat7ConfigurationPacket, 67 | fc2Config, 161 |
| fc2ValidateFormat7Settings, 68 | G , |
| frameCounter | height |
| fc2EmbeddedImageInfo, 167 | fc2Format7ImageSettings, 172 |
| frameRate | fc2GigEImageSettings, 180 |
| fc2AVIOption, 147 | fc2H264Option, 188 |
| fc2H264Option, 188 | highPerformanceRetrieveBuffer |
| • | fc2Config, 161 |
| fc2MJPGOption, 200 | hostPort |
| GPIOPinState | fc2GigEStreamChannel, 186 |
| fc2EmbeddedImageInfo, 167 | iczaigestreamonarmei, 100 |
| GVCP Register Operation, 69 | IIDC specific structures, 137 |
| fc2ReadGVCPMemory, 69 | iidcVer |
| | fc2CameraInfo, 153 |
| fc2ReadGVCPRegister, 70 | |
| fc2ReadGVCPRegisterBlock, 70 | Image Operation, 85 |
| fc2WriteGVCPMemory, 71 | fc2CalculateImageStatistics, 86 |
| fc2WriteGVCPRegister, 71 | fc2ConvertImage, 86 |
| fc2WriteGVCPRegisterBlock, 71 | |
| fc2WriteGVCPRegisterBroadcast, 72 | fc2ConvertImageTo, 87 |
| 102 VVIILE CIVOT Tregister Dioacoast, 72 | fc2CreateImage, 87 |
| gain 1624VilleGVOI NegisterBroadcast, 72 | fc2CreateImage, 87 fc2DestroyImage, 88 |
| | fc2CreateImage, 87 |
| gain | fc2CreateImage, 87 fc2DestroyImage, 88 |
| gain fc2EmbeddedImageInfo, 167 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 fc2GetGigEImageSettings, 75 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 fc2SetDefaultOutputFormat, 93 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 fc2GetGigEImageSettings, 75 fc2GetGigEImageSettingsInfo, 76 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 fc2SetDefaultOutputFormat, 93 fc2SetImageColorProcessing, 93 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 fc2GetGigEImageSettings, 75 fc2GetGigEImageSettingsInfo, 76 fc2GetGigEImagingMode, 76 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageDimensions, 90 fc2GetImageDimensions, 90 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 fc2SetDefaultOutputFormat, 93 fc2SetImageColorProcessing, 93 fc2SetImageColorProcessing, 93 fc2SetImageColorProcessing, 93 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 fc2GetGigEImageSettings, 75 fc2GetGigEImageSettingsInfo, 76 fc2GetGigEImagingMode, 76 fc2QueryGigEImagingMode, 76 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 fc2SetDefaultOutputFormat, 93 fc2SetImageColorProcessing, 93 fc2SetImageData, 93 fc2SetImageDimensions, 94 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 fc2GetGigEImageSettings, 75 fc2GetGigEImageSettingsInfo, 76 fc2GetGigEImagingMode, 76 fc2QueryGigEImagingMode, 76 fc2SetGigEImageSettings, 78 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 fc2SetDefaultOutputFormat, 93 fc2SetImageColorProcessing, 93 fc2SetImageDimensions, 94 Image saving structures., 138 |
| gain fc2EmbeddedImageInfo, 167 General Purpose Input / Output, 38 fc2GetGPIOPinDirection, 38 fc2SetGPIOPinDirection, 39 fc2SetGPIOPinDirectionBroadcast, 39 GetInternal FlyCapture2Private_C.h, 257 GigE image binning settings, 80 fc2GetGigEImageBinningSettings, 80 fc2SetGigEImageBinningSettings, 80 GigE image settings, 75 fc2GetGigEImageSettings, 75 fc2GetGigEImageSettingsInfo, 76 fc2GetGigEImagingMode, 76 fc2QueryGigEImagingMode, 76 | fc2CreateImage, 87 fc2DestroyImage, 88 fc2DetermineBitsPerPixel, 88 fc2GetDefaultColorProcessing, 88 fc2GetDefaultOutputFormat, 89 fc2GetImageColorProcessing, 89 fc2GetImageData, 90 fc2GetImageDimensions, 90 fc2GetImageMetadata, 91 fc2GetImageTimeStamp, 91 fc2SaveImage, 91 fc2SaveImageWithOption, 92 fc2SetDefaultColorProcessing, 92 fc2SetDefaultOutputFormat, 93 fc2SetImageColorProcessing, 93 fc2SetImageData, 93 fc2SetImageDimensions, 94 |

| fc2CallbackHandle, 139 | IsGuiContextValid |
|---------------------------------------|-----------------------------------|
| fc2CameraEventCallback, 139 | FlyCapture2Internal_C.h, 255 |
| fc2ImageEventCallback, 139 | isReadable |
| fc2TIFFCompressionMethod, 139 | fc2GigEProperty, 184 |
| Image Statistics Operation, 95 | isWritable |
| fc2CreateImageStatistics, 96 | fc2GigEProperty, 184 |
| fc2DestroyImageStatistics, 96 | isochBusSpeed |
| fc2GetChannelHistogram, 96 | fc2Config, 161 |
| fc2GetChannelMean, 97 | 10_001g, 10.1 |
| fc2GetChannelNumPixelValues, 97 | libraryList |
| fc2GetChannelPixelValueRange, 98 | fc2SystemInfo, 209 |
| fc2GetChannelRange, 98 | Licensing.dox, 259 |
| fc2GetChannelStatus, 99 | Look Up Table, 51 |
| fc2GetImageStatistics, 99 | fc2EnableLUT, 51 |
| fc2ImageStatisticsDisableAll, 100 | fc2GetActiveLUTBank, 52 |
| fc2ImageStatisticsEnableAll, 100 | fc2GetLUTBankInfo, 52 |
| fc2ImageStatisticsEnableGreyOnly, 100 | fc2GetLUTChannel, 53 |
| fc2ImageStatisticsEnableHSLOnly, 101 | fc2GetLUTInfo, 53 |
| fc2ImageStatisticsEnableRGBOnly, 101 | fc2SetActiveLUTBank, 54 |
| fc2SetChannelStatus, 102 | fc2SetLUTChannel, 54 |
| imageCorrupt | |
| fc2CameraStats, 157 | MAX_STRING_LENGTH |
| imageDriverDropped | MultiSyncLibraryDefs_C.h, 267 |
| fc2CameraStats, 157 | TypeDefs, 115 |
| imageDropped | MULTISYNCLIBRARY_C_API |
| fc2CameraStats, 157 | MultiSyncLibraryPlatform_C.h, 269 |
| | MULTISYNCLIBRARY_C_CALL_CONVEN |
| imageHStepSize | MultiSyncLibraryPlatform_C.h, 269 |
| fc2Format7Info, 174 | macAddress |
| fc2GigEImageSettingsInfo, 182 | fc2CameraInfo, 153 |
| imageImpl | major |
| fc2Image, 189 | fc2Version, 224 |
| imageVStepSize | manualSupported |
| fc2Format7Info, 174 | fc2TriggerDelayInfo, 218 |
| fc2GigEImageSettingsInfo, 182 | max |
| imageXmitFailed | fc2GigEProperty, 184 |
| fc2CameraStats, 157 | fc2TriggerDelayInfo, 218 |
| indexedColor_8bit | maxBytesPerPacket |
| fc2BMPOption, 148 | fc2Format7PacketInfo, 177 |
| Information and Properties, 34 | maxHeight |
| fc2GetCameraInfo, 34 | fc2Format7Info, 175 |
| fc2GetProperty, 34 | fc2GigEImageSettingsInfo, 182 |
| fc2GetPropertyInfo, 35 | maxPacketSize |
| fc2SetProperty, 36 | fc2Format7Info, 175 |
| fc2SetPropertyBroadcast, 36 | maxValue |
| inputBitDepth | fc2StrobeInfo, 206 |
| fc2LUTData, 198 | maxWidth |
| interPacketDelay | fc2Format7Info, 175 |
| fc2GigEStreamChannel, 186 | fc2GigEImageSettingsInfo, 182 |
| interfaceType | maximumBusSpeed |
| fc2CameraInfo, 153 | fc2CameraInfo, 153 |
| interlaced | Memory Channels, 56 |
| fc2PNGOption, 203 | fc2GetEmbeddedImageInfo, 56 |
| ipAddress | fc2GetMemoryChannel, 57 |
| fc2CameraInfo, 153 | fc2GetMemoryChannelInfo, 57 |
| isColorCamera | fc2RestoreFromMemoryChannel, 58 |
| fc2CameraInfo, 153 | fc2SaveToMemoryChannel, 58 |
| IsContextValid | fc2SetEmbeddedImageInfo, 59 |
| FlyCapture2Internal_C.h, 255 | microSeconds |

| fc2TimeStamp, 213 | numCurrents |
|---|-----------------------------------|
| min | fc2CameraStats, 158 |
| fc2GigEProperty, 184 | numEntries |
| fc2TriggerDelayInfo, 218 | fc2LUTData, 198 |
| minNumImageNotifications | numImageNotifications |
| fc2Config, 161 | fc2Config, 162 |
| minPacketSize | numResendPacketsReceived |
| | |
| fc2Format7Info, 175 | fc2CameraStats, 158 |
| minValue | numResendPacketsRequested |
| fc2StrobeInfo, 206 | fc2CameraStats, 158 |
| minor | numVoltages |
| fc2Version, 225 | fc2CameraStats, 158 |
| mode | octets |
| fc2Format7ImageSettings, 172 | fc2IPAddress, 195 |
| fc2Format7Info, 175 | fc2MACAddress, 199 |
| fc2TriggerMode, 220 | |
| modeMask | offsetHStepSize |
| fc2TriggerModeInfo, 222 | fc2Format7Info, 175 |
| modelName | fc2GigElmageSettingsInfo, 182 |
| fc2CameraInfo, 154 | offsetVStepSize |
| MultiSyncLibrary_C.h, 259 | fc2Format7Info, 176 |
| syncCreateContext, 260 | fc2GigEImageSettingsInfo, 182 |
| syncDestroyContext, 260 | offsetX |
| syncDisableCrossPCSynchronization, 260 | fc2Format7ImageSettings, 173 |
| syncEnableCrossPCSynchronization, 261 | fc2GigEImageSettings, 180 |
| syncGetStatus, 261 | offsetY |
| syncGetTimeSinceSynced, 261 | fc2Format7ImageSettings, 173 |
| syncIsTimingBusConnected, 263 | fc2GigEImageSettings, 180 |
| syncQueryCrossPCSynchronizationSetting, 263 | onOff |
| syncRescanMasterTimingBus, 263 | fc2EmbeddedImageInfoProperty, 169 |
| syncStart, 265 | fc2StrobeControl, 205 |
| syncStop, 265 | fc2TriggerDelay, 215 |
| MultiSyncLibraryDefs C.h, 266 | fc2TriggerMode, 220 |
| BOOL, 268 | onOffSupported |
| FALSE, 267 | fc2StrobeInfo, 207 |
| FULL_32BIT_VALUE, 267 | fc2TriggerDelayInfo, 218 |
| MAX_STRING_LENGTH, 267 | fc2TriggerModeInfo, 222 |
| syncContext, 268 | onePush |
| syncError, 268 | fc2TriggerDelay, 215 |
| syncMessage, 268 | onePushSupported |
| TRUE, 267 | fc2TriggerDelayInfo, 218 |
| MultiSyncLibraryPlatform_C.h, 269 | osDescription |
| MULTISYNCLIBRARY_C_API, 269 | fc2SystemInfo, 210 |
| MULTISYNCLIBRARY C CALL CONVEN, 269 | osType |
| MULTISTNOLIBRART_C_CALL_CONVEN, 209 | fc2SystemInfo, 210 |
| networkInterfaceIndex | outputBitDepth |
| fc2GigEStreamChannel, 186 | fc2LUTData, 198 |
| nodeNumber | ICZEOTDala, 190 |
| fc2CameraInfo, 154 | pBusMgr |
| nodeVendorld | fc2InternalContext, 193 |
| fc2ConfigROM, 164 | pCallback |
| numBanks | • |
| | fc2InternalImageCallback, 194 |
| fc2LUTData, 198 | pCallbackData |
| numBuffers | fc2InternalImageCallback, 194 |
| fc2Config, 162 | pCamera |
| numChannels | fc2InternalContext, 193 |
| fc2LUTData, 198 | pCameraControlDlg |
| numCpuCores | fc2InternalGuiContext, 193 |
| fc2SystemInfo, 209 | pCameraSelectionDlg |

| fc2InternalGuiContext, 193 | regWriteFailed |
|-------------------------------|-------------------------------|
| pData | fc2CameraStats, 158 |
| fc2Image, 189 | Register Operation, 60 |
| pUnitAbbr | fc2GetRegisterString, 60 |
| fc2TriggerDelayInfo, 219 | fc2ReadRegister, 60 |
| pUnits | fc2ReadRegisterBlock, 61 |
| fc2TriggerDelayInfo, 219 | fc2WriteRegister, 62 |
| packetSize | fc2WriteRegisterBlock, 62 |
| fc2Format7Info, 176 | fc2WriteRegisterBroadcast, 63 |
| fc2GigEStreamChannel, 186 | registerTimeout |
| parameter | fc2Config, 162 |
| fc2TriggerMode, 220 | fc2GigEConfig, 179 |
| pcieBusSpeed | registerTimeoutRetries |
| fc2CameraInfo, 154 | fc2Config, 162 |
| percentage | fc2GigEConfig, 179 |
| fc2Format7Info, 176 | reserved |
| pixelFormat | fc2AVIOption, 147 |
| fc2Format7ImageSettings, 173 | fc2BMPOption, 148 |
| fc2GigEImageSettings, 180 | fc2CameraInfo, 154 |
| pixelFormatBitField | fc2CameraStats, 159 |
| fc2Format7Info, 176 | fc2Config, 163 |
| fc2GigEImageSettingsInfo, 183 | fc2ConfigROM, 164 |
| polarity | fc2Format7ImageSettings, 173 |
| fc2StrobeControl, 205 | fc2Format7Info, 176 |
| fc2TriggerMode, 221 | fc2Format7PacketInfo, 178 |
| polaritySupported | fc2GigEConfig, 179 |
| fc2StrobeInfo, 207 | fc2GigEImageSettings, 181 |
| fc2TriggerModeInfo, 222 | fc2GigEImageSettingsInfo, 183 |
| portErrors | fc2GigEProperty, 184 |
| fc2CameraStats, 158 | fc2GigEStreamChannel, 187 |
| | fc2H264Option, 188 |
| present fo@Strobolnto 207 | fc2ImageMetadata, 192 |
| fc2StrobeInfo, 207 | _ |
| fc2TriggerDelay, 215 | fc2JPEGOption, 196 |
| fc2TriggerDelayInfo, 218 | fc2JPG2Option, 197 |
| fc2TriggerModeInfo, 223 | fc2LUTData, 199 |
| progressive | fc2MJPGOption, 200 |
| fc2JPEGOption, 196 | fc2PGMOption, 201 |
| propType | fc2PNGOption, 203 |
| fc2GigEProperty, 184 | fc2PPMOption, 204 |
| pszKeyword | fc2StrobeControl, 205 |
| fc2ConfigROM, 164 | fc2StrobeInfo, 207 |
| quality | fc2SystemInfo, 210 |
| quality for IDECOption, 106 | fc2TIFFOption, 211 |
| fc2JPEGOption, 196 | fc2TimeStamp, 213 |
| fc2JPG2Option, 197 | fc2TriggerDelay, 215 |
| fc2MJPGOption, 200 | fc2TriggerDelayInfo, 219 |
| ROIPosition | fc2TriggerMode, 221 |
| | fc2TriggerModeInfo, 223 |
| fc2EmbeddedImageInfo, 167 | ResetStats |
| readOutSupported | FlyCapture2_C.h, 240 |
| fc2StrobeInfo, 207 | rows |
| fc2TriggerDelayInfo, 219 | fc2lmage, 190 |
| fc2TriggerModeInfo, 223 | |
| receivedDataSize | screenHeight |
| fc2Image, 190 | fc2SystemInfo, 210 |
| recommendedBytesPerPacket | screenWidth |
| fc2Format7PacketInfo, 177 | fc2SystemInfo, 210 |
| regReadFailed | seconds |
| fc2CameraStats, 158 | fc2TimeStamp, 213 |

| sensorInfo | syncStart |
|--|--|
| fc2CameraInfo, 154 | MultiSyncLibrary_C.h, 265 |
| sensorResolution | syncStop |
| fc2CameraInfo, 154 | MultiSyncLibrary_C.h, 265 |
| serialNumber | sysMemSize |
| fc2CameraInfo, 155 | fc2SystemInfo, 210 |
| shutter | 1020ystommis, 210 |
| fc2EmbeddedImageInfo, 167 | TRUE |
| softwareTriggerSupported | MultiSyncLibraryDefs_C.h, 267 |
| | TypeDefs, 116 |
| fc2TriggerModeInfo, 223 | temperature |
| Source fo@StrobeControl 205 | fc2CameraStats, 159 |
| fc2StrobeControl, 205 | timeSinceBusReset |
| fc2StrobeInfo, 207 | fc2CameraStats, 159 |
| fc2TriggerMode, 221 | timeSinceInitialization |
| sourceMask | fc2CameraStats, 159 |
| fc2TriggerModeInfo, 223 | timeStamp |
| sourcePort | fc2CameraStats, 159 |
| fc2GigEStreamChannel, 187 | timestamp |
| stride | fc2EmbeddedImageInfo, 168 |
| fc2Image, 190 | TopologyNode Operation, 103 |
| Strobe, 48 | fc2CreateTopologyNode, 104 |
| fc2GetStrobe, 48 | fc2DestroyTopologyNode, 104 |
| fc2GetStrobeInfo, 49 | fc2TopologyNodeAddChild, 104 |
| fc2SetStrobe, 49 | fc2TopologyNodeAddPortType, 105 |
| fc2SetStrobeBroadcast, 50 | fc2TopologyNodeAssignGuidToNode, 105 |
| strobePattern | fc2TopologyNodeAssignGuidToNodeEx, 106 |
| fc2EmbeddedImageInfo, 168 | fc2TopologyNodeGetChild, 106 |
| Structures, 134 | fc2TopologyNodeGetDeviceId, 106 |
| subnetMask | fc2TopologyNodeGetGuid, 107 |
| fc2CameraInfo, 155 | fc2TopologyNodeGetInterfaceType, 107 |
| supported | |
| fc2LUTData, 199 | fc2TopologyNodeGetNodeType, 108 |
| syncContext | fc2TopologyNodeGetNumChildren, 108 |
| MultiSyncLibraryDefs_C.h, 268 | fc2TopologyNodeGetNumPorts, 108 |
| SyncCppImageToStruct | fc2TopologyNodeGetPortType, 109 |
| FlyCapture2Internal_C.h, 255 | Trigger, 41 |
| syncCreateContext | fc2FireSoftwareTrigger, 41 |
| MultiSyncLibrary_C.h, 260 | fc2FireSoftwareTriggerBroadcast, 42 |
| syncDestroyContext | fc2GetTriggerDelay, 42 |
| MultiSyncLibrary_C.h, 260 | fc2GetTriggerDelayInfo, 43 |
| syncDisableCrossPCSynchronization | fc2GetTriggerMode, 43 |
| MultiSyncLibrary_C.h, 260 | fc2GetTriggerModeInfo, 44 |
| syncEnableCrossPCSynchronization | fc2SetTriggerDelay, 44 |
| • | fc2SetTriggerDelayBroadcast, 45 |
| MultiSyncLibrary_C.h, 261 | fc2SetTriggerMode, 45 |
| syncError MultiCured ibusers Defe. C.b. 868 | fc2SetTriggerModeBroadcast, 46 |
| MultiSyncLibraryDefs_C.h, 268 | type |
| syncGetStatus | fc2TriggerDelay, 215 |
| MultiSyncLibrary_C.h, 261 | fc2TriggerDelayInfo, 219 |
| syncGetTimeSinceSynced | fc2Version, 225 |
| MultiSyncLibrary_C.h, 261 | TypeDefs, 115 |
| syncIsTimingBusConnected | BOOL, 116 |
| MultiSyncLibrary_C.h, 263 | FALSE, 115 |
| syncMessage | FULL_32BIT_VALUE, 115 |
| MultiSyncLibraryDefs_C.h, 268 | fc2Context, 116 |
| syncQueryCrossPCSynchronizationSetting | fc2GuiContext, 116 |
| MultiSyncLibrary_C.h, 263 | fc2ImageImpl, 116 |
| syncRescanMasterTimingBus | fc2ImageStatisticsContext, 116 |
| MultiSyncLibrary_C.h, 263 | fc2TopologyNodeContext, 117 |

| 6.000 | |
|--------------------------------|------------------------------|
| fc2VideoContext, 117 | fc2EmbeddedImageInfo, 168 |
| MAX_STRING_LENGTH, 115 | width |
| TRUE, 116 | fc2Format7ImageSettings, 173 |
| | fc2GigEImageSettings, 181 |
| unitBytesPerPacket | fc2H264Option, 188 |
| fc2Format7PacketInfo, 178 | |
| unitSWVer | xmlURL1 |
| fc2ConfigROM, 165 | fc2CameraInfo, 155 |
| unitSpecId | xmIURL2 |
| fc2ConfigROM, 164 | fc2CameraInfo, 155 |
| unitSubSWVer | |
| fc2ConfigROM, 165 | |
| userDefinedName | |
| fc2CameraInfo, 155 | |
| Utilities, 110 | |
| fc2CheckDriver, 110 | |
| fc2ErrorToDescription, 111 | |
| fc2GetDriverDeviceName, 111 | |
| fc2GetLibraryVersion, 111 | |
| fc2GetSystemInfo, 112 | |
| fc2LaunchBrowser, 112 | |
| • | |
| fc2LaunchCommand, 113 | |
| fc2LaunchCommandAsync, 113 | |
| fc2LaunchHelp, 113 | |
| value | |
| fc2GigEProperty, 185 | |
| | |
| fc2PGRGuid, 202 | |
| valueReadable | |
| fc2TriggerModeInfo, 223 | |
| valueA | |
| fc2TriggerDelay, 216 | |
| valueB | |
| fc2TriggerDelay, 216 | |
| vendorName | |
| fc2CameraInfo, 155 | |
| vendorPixelFormatBitField | |
| fc2Format7Info, 176 | |
| fc2GigEImageSettingsInfo, 183 | |
| vendorUniqueInfo_0 | |
| fc2ConfigROM, 165 | |
| vendorUniqueInfo_1 | |
| fc2ConfigROM, 165 | |
| vendorUniqueInfo_2 | |
| fc2ConfigROM, 165 | |
| vendorUniqueInfo_3 | |
| fc2ConfigROM, 165 | |
| Video Recording Operation, 141 | |
| • | |
| fc2VideoAVIOpen, 142 | |
| fc2VideoAppend, 141 | |
| fc2VideoClose, 142 | |
| fc2VideoCreate, 142 | |
| fc2VideoDestroy, 143 | |
| fc2VideoH264Open, 143 | |
| fc2VideoMJPGOpen, 144 | |
| fc2VideoSetMaximumSize, 144 | |
| Video saving structures., 146 | |
| | |

 $white \\Balance$